



Server & Services

Assign ip address for router interface



Interface	IP-Address	OK?	Method	Status	Prot
Ethernet0/0	172.16.0.1	YES	manual	up	up
Ethernet0/1	8.0.0.1	YES	manual	up	up
Ethernet0/2	50.0.0.1	YES	manual	up	up
Ethernet0/3	unassigned	YES	TFTP	down	down

Assign ip address for router interface



```
QEMU (Win)
C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>color f0
C:\Documents and Settings\user>ipconfig


Windows IP Configuration

Ethernet adapter Local Area Connection:

    Connection-specific DNS Suffix  . : 
    IP Address. . . . . : 50.0.0.10
    Subnet Mask . . . . . : 255.0.0.0
    Default Gateway . . . . . : 50.0.0.1

C:\Documents and Settings\user>
```

Assign ip address for tty linux server



```
QEMU (Linux-1)
64 bytes from 50.0.0.10: seq=2 ttl=127 time=2.042 ms
64 bytes from 50.0.0.10: seq=3 ttl=127 time=1.523 ms
64 bytes from 50.0.0.10: seq=4 ttl=127 time=1.351 ms

--- 50.0.0.10 ping statistics ---
5 packets transmitted, 5 packets received, 0% packet loss
round-trip min/avg/max = 1.219/1.709/2.411 ms
# ifconfig
eth0      Link encap:Ethernet  HWaddr 50:93:4C:01:AD:00
          inet addr:172.16.0.10  Bcast:172.16.255.255  Mask:255.255.0.0
          UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
          RX packets:26 errors:0 dropped:0 overruns:0 frame:0
          TX packets:26 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1000
          RX bytes:2766 (2.7 KiB)  TX bytes:3287 (3.2 KiB)

lo        Link encap:Local Loopback
          inet addr:127.0.0.1  Mask:255.0.0.0
          UP LOOPBACK RUNNING  MTU:16436  Metric:1
          RX packets:0 errors:0 dropped:0 overruns:0 frame:0
          TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:0
          RX bytes:0 (0.0 B)  TX bytes:0 (0.0 B)
```

Assign ip address for windows server

```
QEMU (Winserver)
C:\Windows\system32\cmd.exe
C:\Users\Admin>ipconfig

Windows IP Configuration


Ethernet adapter Ethernet:

    Connection-specific DNS Suffix  . : 
    Link-local IPv6 Address . . . . . : fe80::9dcc:1a66:96d1:6cb3%3
    IPv4 Address. . . . . : 172.16.0.20
    Subnet Mask . . . . . : 255.255.0.0
    Default Gateway . . . . . : 172.16.0.1


Tunnel adapter isatap.{2523F545-554E-44BA-9326-684149241DC5}:

    Media State . . . . . : Media disconnected
    Connection-specific DNS Suffix  . :
```


Install IIS service in windows server




Access linux webserver from windows pc




Access windows webserver from windows pc




Assign ip in DNS server




Install dns service from server manager




Once installed dns service go to tools and open dns and create record for linux webserver and windows server



Set preferred dns server ip in client device



Access webserver-1 using domain name



Access webserver-2 using domain name

