




Configurer switch 1 and 2

```
Switch1
Physical Config CLI Attributes
IOS Command Line Interface

Switch>enable
Switch#config ter
Enter configuration commands, one per line. End with
CNTL/Z.
Switch(config)#
Switch(config)#
Switch(config)#hostname SW-Floor-1
SW-Floor-1(config)#line console 0
SW-Floor-1(config-line)#password cisco
SW-Floor-1(config-line)#service password-encryption
SW-Floor-1(config)#login
^
% Invalid input detected at '^' marker.

SW-Floor-1(config)#wr
^
% Invalid input detected at '^' marker.

SW-Floor-1(config)#do write
Building configuration...
[OK]
SW-Floor-1(config)#enable secret class
SW-Floor-1(config)#exit
SW-Floor-1#
%SYS-5-CONFIG_I: Configured from console by console

SW-Floor-1#config terminal
Enter configuration commands, one per line. End with
```

```
Switch1
Physical Config CLI Attributes
IOS Command Line Interface

SW-Floor-1#config terminal
Enter configuration commands, one per line. End with
CNTL/Z.
SW-Floor-1(config)#line vty 0 4
SW-Floor-1(config-line)#password cisco
SW-Floor-1(config-line)#login
SW-Floor-1(config-line)#end
SW-Floor-1#
%SYS-5-CONFIG_I: Configured from console by console

SW-Floor-1#do write
^
% Invalid input detected at '^' marker.

SW-Floor-1#config ter
SW-Floor-1#config terminal
Enter configuration commands, one per line. End with
CNTL/Z.
SW-Floor-1(config)#show running-config
^
% Invalid input detected at '^' marker.

SW-Floor-1(config)#show running-config?
% Unrecognized command
SW-Floor-1(config)#do show running-config
Building configuration...
```

```
Switch1
Physical Config CLI Attributes
IOS Command Line Interface

SW-Floor-1(config)#show running-config?
% Unrecognized command
SW-Floor-1(config)#do show running-config
Building configuration...

Current configuration : 1180 bytes
!
version 15.0
no service timestamps log datetime msec
no service timestamps debug datetime msec
service password-encryption
!
hostname SW-Floor-1
!
enable secret 5 $1$mERr$9cTjUIEqNGurQiFU.ZeCi1
!
!
!
!
!
spanning-tree mode pvst
spanning-tree extend system-id
!
interface FastEthernet0/1

SW-Floor-1(config)#
```

```
Switch2
Physical Config CLI Attributes
IOS Command Line Interface

Switch>
Switch>enable
Switch#config terminal
Enter configuration commands, one per line. End with
CNTL/Z.
Switch(config)#hostname SW-Floor-1
SW-Floor-1(config)#
SW-Floor-1(config)#line console 0
SW-Floor-1(config-line)#password cisco
SW-Floor-1(config-line)#login
SW-Floor-1(config-line)#service password-encryption
SW-Floor-1(config)#line vty 0 4
SW-Floor-1(config-line)#password cisco
SW-Floor-1(config-line)#login
SW-Floor-1(config-line)#do write
Building configuration...
[OK]
SW-Floor-1(config-line)#
SW-Floor-1(config-line)#exit
SW-Floor-1(config)#interface range f0/1 - 4
SW-Floor-1(config-if-range)#end
SW-Floor-1#
%SYS-5-CONFIG_I: Configured from console by console

SW-Floor-1#do write
^
% Invalid input detected at '^' marker.
```

Configur Routing 1



```
Router(config)#interface gig0/0/0
^
% Invalid input detected at '^' marker.

Router(config)#interface gig0/0/0
Router(config-if)#ipv6 address 2001:db8:acad:1::1/64
Router(config-if)#ipv6 unicast-routing
Router(config)#ipv6 address 2001:db8:acad:1::1/64
^
% Invalid input detected at '^' marker.


Router(config)#
Router(config)#
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
Router#cofig terminal
Router#cofig terminal
^
% Invalid input detected at '^' marker.

Router#config terminal
Router#config terminal
^
% Invalid input detected at '^' marker.
```



IPv6 for all labs



Laptop3

PhysicalConfigDesktopProgrammingAttributes

IP ConfigurationX

InterfaceFastEthernet0

IP Configuration

DHCPStatic

IPv4 Address

Subnet Mask

Default Gateway0.0.0.0

DNS Server0.0.0.0

IPv6 Configuration

AutomaticStatic

IPv6 Address2001:db8:acad:1::13 / 64

Link Local AddressFE80::2D0:58FF:FEA7:8E5

Default Gateway2001:db8:acad:1::1

DNS Server

Laptop2

PhysicalConfigDesktopProgrammingAttributes

IP ConfigurationX

InterfaceFastEthernet0

IP Configuration

DHCPStatic

IPv4 Address

Subnet Mask

Default Gateway0.0.0.0

DNS Server0.0.0.0

IPv6 Configuration

AutomaticStatic

IPv6 Address2001:db8:acad:1::12 / 64

Link Local AddressFE80::2D0:FFFF:FE95:928C

Default Gateway2001:db8:acad:1::1|

DNS Server

Laptop5

PhysicalConfigDesktopProgrammingAttributes

IP ConfigurationX

InterfaceFastEthernet0

IP Configuration

DHCPStatic

IPv4 Address

Subnet Mask

Default Gateway0.0.0.0

DNS Server0.0.0.0

IPv6 Configuration

AutomaticStatic

IPv6 Address2000db8:acad:1::12 / 64

Link Local AddressFE80::2D0:FFFF:FEDA:2372

Default Gateway2000:db8:acad:1::1

DNS Server

Laptop4

PhysicalConfigDesktopProgrammingAttributes

IP ConfigurationX

InterfaceFastEthernet0

IP Configuration

DHCPStatic

IPv4 Address

Subnet Mask

Default Gateway0.0.0.0

DNS Server0.0.0.0

IPv6 Configuration

AutomaticStatic

IPv6 Address2000:db8:acad:1::11 / 64

Link Local AddressFE80::207:ECFF:FEC5:1CD2

Default Gateway2000:db8:acad:1::1|

DNS Server

Laptop6

PhysicalConfigDesktopProgrammingAttributes

IP ConfigurationX

InterfaceFastEthernet0

IP Configuration

DHCPStatic

IPv4 Address

Subnet Mask

Default Gateway0.0.0.0

DNS Server0.0.0.0

IPv6 Configuration

AutomaticStatic

IPv6 Address2000:db8:acad:1::13 / 64

Link Local AddressFE80::201:42FF:FEC6:38A1

Default Gateway2000:db8:acad:1::1|

DNS Server

Test connection with ping protocol

