



R1



```
R1(config)#
R1(config)#
R1(config)#
R1(config)#int e0/0
R1(config-if)#ip add 50.0.0.1 255.0.0.0
R1(config-if)#no sh
R1(config-if)#ex
R1(config)#
R1(config)#int e0/1
R1(config-if)#ip add 172.16.0.1 255.255.0.0
R1(config-if)#no sh
R1(config-if)#ex
R1(config)#
R1(config)#
R1(config)#
R1(config)#
R1(config)#
R1(config)#
R1(config)#
R1(config)# ip route 192.168.2.0 255.255.255.0 172.16.0.2
R1(config)#
```


Gateway of last resort is not set

50.0.0.0/8 is variably subnetted, 2 subnets, 2 masks

C 50.0.0.0/8 is directly connected, Ethernet0/0

L 50.0.0.1/32 is directly connected, Ethernet0/0

172.16.0.0/16 is variably subnetted, 2 subnets, 2 masks

C 172.16.0.0/16 is directly connected, Ethernet0/1

L 172.16.0.1/32 is directly connected, Ethernet0/1

S 192.168.2.0/24 [1/0] via 172.16.0.2

R1#show ip int brief

Interface	IP-Address	OK?	Method	Status	Prot
Ethernet0/0	50.0.0.1	YES	manual	up	up
Ethernet0/1	172.16.0.1	YES	manual	up	up
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

R2

I

```
R2#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#int e0/0
R2(config-if)#ip add 192.168.2.1 255.255.255.0
R2(config-if)#no sh
R2(config-if)#
R2(config-if)#ex
R2(config)#
R2(config)#int e0/1
R2(config-if)#ip add 172.16.0.2 255.255.0.0
R2(config-if)#no sh
R2(config-if)#ex
R2(config)#
R2(config)#
R2(config)#ip route 50.0.0.0 255.0.0.0 172.16.0.1
R2(config)#
```


i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

S 50.0.0.0/8 [1/0] via 172.16.0.1
172.16.0.0/16 is variably subnetted, 2 subnets, 2 masks
C 172.16.0.0/16 is directly connected, Ethernet0/1
L 172.16.0.2/32 is directly connected, Ethernet0/1
192.168.2.0/24 is variably subnetted, 2 subnets, 2 masks
C 192.168.2.0/24 is directly connected, Ethernet0/0
L 192.168.2.1/32 is directly connected, Ethernet0/0

R2#show ip int brief

Interface	IP-Address	OK?	Method	Status	Prot
Ethernet0/0	192.168.2.1	YES	manual	up	up
Ethernet0/1	172.16.0.2	YES	manual	up	up
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

R2#

R1

```
R1(config)#  
R1(config)#  
R1(config)#  
R1(config)#  
R1(config)#  
R1(config)#  
R1(config)#  
R1(config)#ip dhcp pool HR  
R1(dhcp-config)#network 50.0.0.0 255.0.0.0  
R1(dhcp-config)#default-router 50.0.0.1  
R1(dhcp-config)#dns-server 8.8.8.8  
R1(dhcp-config)#lease 1 2 3  
R1(dhcp-config)#exit  
R1(config)#  
R1(config)#  
R1(config)#ip dhcp excluded-address 50.0.0.1 50.0.0.50  
R1(config)#  
R1(config)#  
R1(config)#  
R1(config)#
```


Welcome to Virtual PC Simulator, version 1.3 (0.8.1)

Dedicated to Daling.

Build time: May 7 2022 15:27:29

Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)

Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)

All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.

Source code and license can be found at vpcs.sf.net.

For more information, please visit wiki.freecode.com.cn.

Modified version for EVE-NG.


Press '?' to get help.

Executing the startup file

VPC-1> ip dhcp

DDORA IP 50.0.0.51/8 GW 50.0.0.1

VPC-1> █



R1



```
R1(config)#
```

```
R1(config)#
```

```
R1(config)#
```

```
R1(config)#ip dhcp pool HR
```

```
R1(dhcp-config)#network 50.0.0.0 255.0.0.0
```

```
R1(dhcp-config)#default-router 50.0.0.1
```

```
R1(dhcp-config)#dns-server 8.8.8.8
```

```
R1(dhcp-config)#lease 1 2 3
```

```
R1(dhcp-config)#exit
```

```
R1(config)#
```

```
R1(config)#
```

```
R1(config)#ip dhcp excluded-address 50.0.0.1 50.0.0.50
```

```
R1(config)#
```

```
R1(config)#
```

```
R1(config)#
```

```
R1(config)#
```

```
R1(config)#exit
```

```
R1#sh
```

```
*Sep  2 03:28:26.136: %SYS-5-CONFIG_I: Configured from console by console
```

```
R1#show ip dhcp binding
```

```
Bindings from all pools not associated with VRF:
```

IP address	Client-ID/ Hardware address/ User name	Lease expiration	Type
50.0.0.51	0100.5079.6668.da	Sep 03 2026 10:59 AM	Automatic

```
R1#
```




R1



```
R1#
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#
R1(config)#
R1(config)#
R1(config)#ip dhcp pool SALES
R1(dhcp-config)#network 192.168.2.0
R1(dhcp-config)#network 192.168.2.0 255.255.255.0
R1(dhcp-config)#default-router 192.168.2.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2
R1(dhcp-config)#exit
R1(config)#
R1(config)#
R1(config)#
R1(config)#ip dhcp excluded-address 192.168.2.1 192.168.2.50
R1(config)#
```


R2

```
R2(config)#int e0/0
R2(config-if)#ip helper-address 172.16.0.1
R2(config-if)#
```


QEMU (Win)



My Documents



My Computer



My Network Places



Recycle Bin



Internet Explorer

Network Connections

File Edit View Favorites Tools Advanced Help



Address Network Connections




Network Tasks

- Create a new connection
- Set up a home or small office network
- Change Windows Firewall settings
- Enable this network device
- Rename this connection
- Change settings of this connection

LAN or High-Speed Internet



Local Area Connection
Disabled
Intel(R) PRO/1000 MT Networ...





My Documents



My Computer

My Network
Places

Recycle Bin

Internet
ExplorerCisco
ASDM

C:\WINDOWS\system32\cmd.exe

Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

Connection-specific DNS Suffix	:	:
IP Address	:	192.168.2.51
Subnet Mask	:	255.255.255.0
Default Gateway	:	192.168.2.1

C:\Documents and Settings\user>_