

Pinout & Configuration

Clock Configuration

▼ Software Packs

▼ Pinout



Categories A->Z

System Core >

Analog >

Timers >

Connectivity ▼

CAN

✓ I2C1

I2C2

SPI1

SPI2

USART1

✗ USART2

USART3

USB

Computing >

Middleware and Software Packs >

I2C1 Mode and Configuration

Mode

I2C I2C ▼

Configuration

Reset Configuration

✓ Parameter Settings

✓ User Constants

✓ NVIC Settings

✓ DMA Settings

✓ GPIO Settings

Configure the below parameters :



▼ Master Features

I2C Speed Mode

Standard Mode

I2C Clock Speed (Hz)

100000

▼ Slave Features

Clock No Stretch Mode

Disabled

Primary Address Length selection

7-bit

Dual Address Acknowledged

Disabled

Primary slave address

0

General Call address detection

Disabled

Pinout & Configuration

Clock Configuration

▼ Software Packs

▼ Pinout

Q 

Categories

A->Z

System Core >

Analog >

Timers ▼

RTC

TIM1

TIM2

✓ TIM3

⚠ TIM4

Connectivity >

Computing >

Middleware and Software Packs >

TIM3 Mode and Configuration

Mode

Slave Mode Trigger Source ☒ Internal ClockChannel1 Channel2 Channel3 Channel4 Combined Channels ☐ XOR activation☐ One Pulse Mode

Configuration

Reset Configuration

✓ Parameter Settings

✓ User Constants

✓ NVIC Settings

✓ DMA Settings

Configure the below parameters :

Q 

▼ Counter Settings

Prescaler (PSC - 16 bits value) 7999

Counter Mode Up

Counter Period (AutoReload Register - 16 bits... 499

Internal Clock Division (CKD) No Division

auto-reload preload Disable

▼ Trigger Output (TRGO) Parameters

Master/Slave Mode (MSM bit) Disable (Trigger input effect not delayed)

Trigger Event Selection Reset (UG bit from TIMx_EGR)

Pinout & Configuration

Clock Configuration

v Software Packs

v Pinout

Q



Categories A->Z

System Core >

Analog >

Timers v

RTC

TIM1

TIM2

✓ TIM3

⚠ TIM4

Connectivity v

CAN

✓ I2C1

I2C2

SPI1

SPI2

USART1

⊗ USART2

USART3

USB

Computing >

Middleware and Software Packs >

TIM3 Mode and Configuration

Mode

Slave Mode Disable v

Trigger Source Disable v

☒ Internal Clock

Channel1 Disable v

Channel2 Disable v

Channel3 Disable v

Channel4 Disable v

Combined Channels Disable v

☐ XOR activation☐ One Pulse Mode

Configuration

Reset Configuration

✓ Parameter Settings ✓ User Constants ✓ NVIC Settings ✓ DMA Settings

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
TIM3 global interrupt	☒	0	0

Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

Pinout view

System view

Categories A-Z

- System Core >
- Analog >
- Timers >
- Connectivity >
- Computing >
- Middleware and Software Packs >

