

Experiment 7 Establishing Metrics (KPIs and KRIs)

01/08/2026

Aim

To configure a risk measurement method in Eramba and establish measurable risk indicators using Likelihood, Impact, and Risk Score.

Procedure

1. Navigate to **Risk Management** → **Settings** → **Calculation Method**.
2. Select the **Threshold** calculation method.
3. Enable the **Threshold** method.
4. Verify that the calculation uses $Likelihood \times Impact$.
5. Ensure the required Likelihood and Impact classifications are configured.
6. Save the calculation method.
7. Open **Business Risks**.
8. Open a configured risk, such as **Business Interruption**.
9. Navigate to the **Analysis** section.
10. Verify the **Risk Analysis Classification** and the resulting **Risk Analysis Score**.

Output

The Threshold calculation method was successfully configured using a Likelihood $\times$ Impact matrix. The system calculates a numerical risk score based on the selected classifications.

The screenshot displays the 'Edit Action' window for the 'Threshold' calculation method. The 'Enable' toggle is turned on. The 'Method Name' is 'Threshold'. The 'Settings' section shows 'Likelihood $\times$ Impact' as the selected calculation method. Below this, a table defines the threshold values for different likelihood and impact combinations. The table has two rows: '[Default Threshold] Not configured' and 'Impact (Very High)'. The columns represent likelihood levels: 'Likelihood (Low)', 'Likelihood (Medium)', 'Likelihood (Very High)', and 'Likelihood (High)'. Each cell in the table contains a message: 'Threshold is not configured, eramba will use default threshold configuration for this matrix'. The 'Save' button is visible at the bottom right.

	Likelihood (Low)	Likelihood (Medium)	Likelihood (Very High)	Likelihood (High)
[Default Threshold] Not configured				
Impact (Very High)	Threshold is not configured, eramba will use default threshold configuration for this matrix	Threshold is not configured, eramba will use default threshold configuration for this matrix	Threshold is not configured, eramba will use default threshold configuration for this matrix	Threshold is not configured, eramba will use default threshold configuration for this matrix

Fig 7.1 – Threshold Calculation Method Configuration (Likelihood × Impact Matrix)

The screenshot shows a web application interface for risk analysis. At the top, there are tabs for 'Business Risks' and 'Reviews'. Below the tabs is a breadcrumb trail: '← Back'. The main heading is 'Business Interruption'. Underneath is a section titled 'Item detail'. The 'Analysis' section is highlighted in light blue and contains several input fields: 'Applicable Business Units' (with a dropdown menu showing 'Operations'), 'Processes', 'Threat Type', 'Threat Description', 'Vulnerability Type', and 'Vulnerability Description'. Below these fields is a 'Risk Analysis Classification' section with two buttons: 'Likelihood (Medium)' and 'Impact (Very High)'. The 'Risk Analysis Score' is displayed as '6', and the 'Risk Analysis Threshold' is shown as a horizontal bar chart.

Fig 7.2 – Risk Analysis Classification & Score (Business Interruption)

Result

The risk measurement system was successfully established. For the selected Business Risk, Likelihood (Medium) + Impact (Very High) produced a Risk Analysis Score of 6, demonstrating that risk indicators can be measured consistently.