Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Akamai Connectors

Connectors allow Stellar Cyber to collect data from external sources and add it to the data lake.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Akamai

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records

Admin Events Reports
Audit Logs Reports
Connectors
Users
	Syslog
	Assets (for Connectors)
		msg_class:
		`akamai_eaa_admin_events_reports`
		`akamai_eaa_audit_logs_reports`
		`akamai_eaa_connectors`
		`akamai_eaa_users`
		
		msg_origin.source:
		`akamai_eaa`
		
		msg_origin.vendor:

Content Type	Index	Locating Records

		`akamai`
		
		msg_origin.category:
		`endpoint`

Domain

https://<Hostname>

where <Hostname> is a variable from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Hostname, Access Token, Client Token, Client Secret, and Contract ID

Adding an Akamai Connector

To add an Akamai connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Obtaining Akamai Credentials

To create the Akamai API credentials:

 Use our example as a guideline, as you might be using a different software version.


1. Log in to your **Akamai Control Center** account (https://control.akamai.com).
2. Navigate to **Identity & Access > New API Client for Me**.
3. Select which roles, contracts, and groups you are using with the Stellar Cyber API client. You will need to note the **Contract ID** for use with the connector.
4. Select **HTTPie** for the tool you will use for the API requests.
5. Select the permissions as **read-only**.
6. Click **Submit**.
7. When displayed, copy the **base URL**.

8. Click on the **New Credential** button and copy or download your **Access Token**, **Client Token**, and **Client Secret**.
9. Save all of the above information before proceeding to the next section.


Adding the Connector in Stellar Cyber

After completing the previous section, with the required credentials noted, you can add the Akamai connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System** | **INTEGRATIONS** | **Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **Akamai** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

Notes:

- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.




The asterisk (*) indicates a required field.

12. Enter the **Hostname**.

Do not include https in the hostname.

For release versions prior to v4.3.4, ensure the URL does not include a trailing "/" symbol.

13. Enter the **Access Token** you noted above in Obtaining Akamai Credentials.
14. Enter the **Client Token** you noted above.
15. Enter the **Client Secret** you noted above.
16. Enter the **Contract ID** you noted above.
17. Choose the **Interval (min)**. This is how often the logs are collected.
18. Choose the **Content Type** you would like to collect. The supported content types are:
    - Admin Events Reports
    - Audit Logs Reports
    - Connectors
    - Users
19. Click **Next**. The final confirmation tab appears.



20. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** for the type of content you collected:
   - For all content types, change the **Indices** to **Syslog**.
   - For **Connectors** only, change the **Indices** to **Assets**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.