Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

# Configuring BeyondTrust Connectors 6.1.0

This connector allows Stellar Cyber to ingest logs from BeyondTrust and add the records to the data lake. It integrates with the BeyondTrust API to query for support session reports.

Logs and alerts are sent to Stellar Cyber based on real-time monitoring and detection of unauthorized remote access attempts by tracking user activities, identifying anomalies like failed logins or unusual behaviors, and triggering automated responses such as session termination or account locking.

Note the following rate limit: Requests are limited to 20 per second and 15,000 per hour. This limit applies to all API endpoints and is per API account.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

## Connector Overview: BeyondTrust

### Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

### Collected Data

| Content Type | Index | Locating Records |
|---|---|---|
| Support Session Reports | Syslog | msg_class: `beyondtrust_remote_support_support_session_reports`<br><br>msg_origin.source: |

| Content Type | Index | Locating Records |
| --- | --- | --- |
|  | | `beyondtrust_remote_support`<br><br>msg_origin.vendor:<br>`beyondtrust`<br><br>msg_origin.category:<br>`pam` |

### Domain

<Base URL>

where <Base URL> is a variable from the configuration of this connector

### Response Actions

N/A

### Third Party Native Alert Integration Details

N/A

### Required Credentials and Configurations

- Base URL, Client ID, and Client Secret

## Adding a BeyondTrust Connector

To add a BeyondTrust connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

## Obtaining BeyondTrust Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following BeyondTrust credentials:

- Base URL—The base URL for API access. Go to BeyondTrust's Pathfinder to find your base URL. This is an example: https://bvrc.beyondtrustcloud.com.
- Client ID and Client Secret—The authentication credentials. See Getting the Client ID and Client Secret.

### Getting the Client ID and Client Secret

To authenticate to the API, you must create an API account on the **/login > Management > API Configuration** page. The account must have permission to access the necessary APIs. Follow the guidance in the BeyondTrust documentation to Create an API account.

Also, refer to the following notes in the BeyondTrust documentation to Authenticate to the API.

**Note**

This token expires after one hour. Any calls to the API past that point must ha token. Each API account can have a maximum of 30 valid tokens. If an API account attempts to generate more than 30 tokens, then the oldest token is invalidated before a new one is generated.


**Note**

The client secret cannot be modified, but it can be regenerated on the **/login > Management > API Configuration** page. Regenerating a client secret and then saving the account immediately invalidates any OAuth tokens associated with the account. Any API calls using those tokens will be unable to access the API. A new token must be generated using the new client secret.


# Adding the Connector in Stellar Cyber

To add a BeyondTrust connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.




The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Privileged Access Management** from the **Category** dropdown.
5. Choose **BeyondTrust** from the **Type** dropdown.




The asterisk (*) indicates a required field.


6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

Notes:

- This field does not accept multibyte characters.


- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.




The asterisk (*) indicates a required field.

12. Select the **Base URL** you noted above in Obtaining BeyondTrust Credentials.
13. Enter the **Client ID** you noted above.
14. Enter the **Client Secret** you noted above.
15. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
16. Choose the **Interval (min)**. This is how often the logs are collected.
17. Choose the **Content Type** you would like to collect. The logs for **Support Session Reports** are supported.
18. Click **Next**. The final confirmation tab appears.




19. Click **Submit**.

The new connector is immediately active.


## Testing the Connector

In addition to testing for connectivity, the **Test** button for the BeyondTrust connector tests that the Base URL, Client ID, and Client Secret are correct and data requests for the requested content types return successful responses.

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !




Failure with summary of issue:




Show More example detail:




If the test fails, the common HTTP status error codes are as follows:

| HTTP Error Code | HTTP Standard Error Name | Explanation | Recommendation |
|---|---|---|---|
| 400 | Bad Request | This error occurs when there is an error in the connector configuration. | Did you configure the connector correctly? |
| 401 | Unauthorized | This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API. | Did you enter your credentials correctly?<br>Are your credentials expired?<br>Are your credentials entitled or licensed for that specific resource? |
| 403 | Forbidden | This error occurs when the permission or scope is not correct in a valid credential. | Did you enter your credentials correctly?<br>Do you have the required role or permissions for that credential? |
| 404 | Not Found | This error occurs when a URL path does not resolve to an entity. | Did you enter your API URL correctly? |
| 429 | Too Many Requests | This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded. | The server or user license/quota will eventually recover. The connector will periodically retry the query.<br>If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas. |

For a full list of codes, refer to HTTP response status codes.

# Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog**.

   The table immediately updates to show ingested Interflow records.


© 2026 Stellar Cyber . All rights reserved.