Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring NetFoundry Connectors

This connector allows Stellar Cyber to ingest logs from NetFoundry and add the records to the data lake. This connector integrates with the NetFoundry API to query API session events and audit logs.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: NetFoundry

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records

API Session Events
Audit Logs
	Syslog	msg_class:
		`netfoundry_api_session_event`
		`netfoundry_audit_log`
		
		msg_origin.source:
		`netfoundry`
		
		msg_origin.vendor:
		`netfoundry`

Content Type	Index	Locating Records
		msg_origin.category: `sase`

Domain

<Auth URL> and <Base URL>

where <Auth URL> and <Base URL> are variables from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Auth URL, Base URL, Client ID, Password, Network Group ID, and Network ID

Adding a NetFoundry Connector

To add a NetFoundry connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Obtaining NetFoundry Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following NetFoundry credentials that map to the Stellar Cyber fields:

NetFoundry	Definition	Stellar Cyber Fields
NETFOUNDRY_OAUTH_URL	Authentication URL.	Auth URL
BASE_URL	Base URL: https://gateway.production.netfoundry.io/	Base URL
NETFOUNDRY_CLIENT_ID	Unique identifier used to authenticate a NetFoundry client application.	Client ID
NETFOUNDRY_PASSWORD	Secret key used with the client ID.	Password
NETWORK_GROUP_ID	Collection of networks grouped together for administrative purposes.	Network Group ID
NETWORK_ID	Unique identifier for a specific network in your NetFoundry account. A network belongs to one	Network ID

network group and is identified by its unique
twork ID within that group.

Get an API Account

To get an API account, follow the guidance in the NetFoundry documentation in the Authentication section for Get an API Account. The following information is in the credentials.json file you download:

```
"clientId": "xxxx",
"password": "xxxxxxxxx",
"authenticationUrl": "https://xxxxxxx/oauth2/token"
```

Get the Network ID

To get the Network ID:

1. Log in to the NetFoundry web console at console.netfoundry.io and log in with your credentials.
2. Navigate to the **Networks** tab to see a list of all the networks associated with your account.
3. Locate the Network ID in the list of networks. You should see details like Network Name, Network ID, and other relevant information. The Network ID is usually displayed alongside the network's name or in the network details page.

Get the Network Group ID


To get the Network Group ID:

1. Log in to the NetFoundry web console at console.netfoundry.io and log in with your credentials.
2. Navigate to **Network Groups** in the dashboard under the **Networks** tab, depending on your account permissions and console version.
3. Locate the Network Group ID in the list of network groups. The Network Group ID is often displayed alongside each group's name or within its detailed view.


Adding the Connector in Stellar Cyber

To add a NetFoundry connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **SASE** from the **Category** dropdown.
5. Choose **NetFoundry** from the **Type** dropdown.




   The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.


8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



   The asterisk (*) indicates a required field.

12. Enter the **Auth URL** you noted above in Obtaining NetFoundry Credentials.
13. Enter the **Base URL** you noted above.

14. Enter the **Client ID** you noted above.
15. Enter the **Password** you noted above.
16. Enter the **Network Group ID** you noted above.
17. Enter the **Network ID** you noted above.
18. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
19. Choose the **Interval (min)**. This is how often the logs are collected.
20. Choose the **Content Type** you would like to collect. The logs for **API Session Events** and **Audit Logs** are supported.
21. Click **Next**. The final confirmation tab appears.



22. Click **Submit**.

The new connector is immediately active.


Testing the Connector

In addition to testing for connectivity, the **Test** button for the NetFoundry connector tests that the Auth URL, Client ID, and Password are correct and an access token can be created. The data requests for the requested content types return successful responses, which verifies that the granted access token has the correct permissions and the provided Network Group ID is valid.

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.