

Question 3


Class C subnet mask 255.255.255.0


Research -> 192.168.1.254
HR -> 192.168.2.254
Admin -> 192.168.3.254





Enable
Configure terminal
Interface FastEthernet1/0
Ip address 192.168.1.254 255.255.255.0
No shutdown
Exit
Exit


R1
R1(config)#interface FastEthernet1/0
R1(config-if)#ip address 192.168.1.254 255.255.255
% Incomplete command.
R1(config-if)#ip address 192.168.1.254 255.255.255.0
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#exit
R1#
*Mar 1 00:01:53.747: %LINK-3-UPDOWN: Interface FastEthernet1/0, changed state to up
*Mar 1 00:01:54.747: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up
R1#e
*Mar 1 00:01:55.467: %SYS-5-CONFIG_I: Configured from console by console
R1#enable
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#interface FastEthernet0/0
R1(config-if)#ip address 192.168.2.254 255.255.255.0
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#exi
*Mar 1 00:02:54.975: %LINK-3-UPDOWN: Interface FastEthernet0/0, changed state to up
*Mar 1 00:02:55.975: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
R1(config)#exit
R1#ena
*Mar 1 00:02:59.199: %SYS-5-CONFIG_I: Configured from console by console
R1#enable configure
^
% Invalid input detected at '^' marker.
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#interface FastEhernet0/1
^
% Invalid input detected at '^' marker.
solarwinds
Solar-PuTTY free tool
© 2019-2024 SolarWinds Worldwide, LLC. All rights reserved.





```
R1(dhcp-config)#exit
R1(config)#exit
R1#sho
*Mar  1 00:07:05.739: %SYS-5-CONFIG_I: Configured from console by console
R1#show ip interface brief
Interface                  IP-Address      OK? Method Status                Protocol
FastEthernet0/0            192.168.2.254   YES manual up                    up
FastEthernet0/1            192.168.3.254   YES manual up                    up
FastEthernet1/0            192.168.1.254   YES manual up                    up
Serial2/0                  unassigned      YES unset  administratively down down
Serial2/1                  unassigned      YES unset  administratively down down
Serial2/2                  unassigned      YES unset  administratively down down
Serial2/3                  unassigned      YES unset  administratively down down
R1#
```


enable
configure terminal
ip dhcp pool hr


network 192.168.2.0 255.255.255.0
default-router 192.168.2.254

exit
ip dhcp excluded-address 192.168.2.254



We communicate the two pc, research and administration


R1
PC5
PC26
Welcome to Virtual PC Simulator, version 0.6.2
Dedicated to Daling.
Build time: Apr 10 2019 02:42:20
Copyright (c) 2007-2014, Paul Meng (mirnshi@gmail.com)
All rights reserved.
VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Press '?' to get help.
Executing the startup file
PC5> ip dhcp
DDORA IP 192.168.1.1/24 GW 192.168.1.254
PC5> ping 192.168.3.1
192.168.3.1 icmp_seq=1 timeout
192.168.3.1 icmp_seq=2 timeout
84 bytes from 192.168.3.1 icmp_seq=3 ttl=63 time=32.086 ms
84 bytes from 192.168.3.1 icmp_seq=4 ttl=63 time=31.752 ms
84 bytes from 192.168.3.1 icmp_seq=5 ttl=63 time=30.299 ms
PC5>


R1
PC5
PC26
Welcome to Virtual PC Simulator, version 0.6.2
Dedicated to Daling.
Build time: Apr 10 2019 02:42:20
Copyright (c) 2007-2014, Paul Meng (mirnshi@gmail.com)
All rights reserved.
VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Press '?' to get help.
Executing the startup file
PC26> ping 192.168.1.1
host (192.168.1.1) not reachable
PC26> ip dhcp
DDORA IP 192.168.3.1/24 GW 192.168.3.254
PC26>