## **UNIVERSITY OF KARACHI**



# **ASSEMBLY LANGUAGE PROGRAMMING**

BSCS-403

Name of Student: MUHAMMAD AMAS

Seat No: B20102077

Class Roll No: 34

Section: A

Semester No: 3rd

Submitted to: MS FARHEEN FAISAL SIDDIQUI

## **DEPARTMENT OF COMPUTER SCIENCE**

UNIVERSITY OF KARACHI

### 1. USING LOOP: PROGRAM TO PRINT 0 TO 9

```
File Edit Search View Options Help
                                 C:NW61.ASM
 DOSSEG
 MODEL SMALL
              :MODEL DIRECTIVE
 .STACK 100H
              :STACK SEGMENT DIRECTIVE
              : UARIABLE DECLERATION
 .DATA
 .CODE
              :CODE SPACE
 MAIN PROC
 MOU CX,10
              COUNTER FOR 10 TIMES
 MOV DX,48
 L1:
 MOV AH,2
 INT 21H
 ADD DX,1
              : INCREMENT +1
 LOOP L1
 MOV AH,4CH :TO EXIT THE REGISTER
 INT 21H
 MAIN ENDP
 END MAIN
F1=Help
                                                                Col:1
                                                      Line:1
C:N>MASM W61.ASM;
Microsoft (R) Macro Assembler Version 5.00
Copyright (C) Microsoft Corp 1981–1985, 1987. All rights reserved.
 51720 + 464824 Bytes symbol space free
     0 Warning Errors
     O Severe Errors
C:\>LINK W61.OBJ;
Microsoft (R) Overlay Linker Version 3.60
Copyright (C) Microsoft Corp 1983-1987. All rights reserved.
C:\>W61.EXE
0123456789
C:\>_
```

## 2. Using LOOP: Program to print A to Z

```
File Edit Search View Options Help
                                 C:NW62.ASM
 DOSSEG
 .MODEL SMALL :MODEL DIRECTIVE
 .STACK 100H
              :STACK DIRECTIVE
              : UARIABLE DECLERATION
 .DATA
 .CODE
              :CODE SPACE
 MAIN PROC
 MOV CX,26
              :LOOP RUN 26 TIMES
MOV DX,65
              :ASCII CODE OF A
 L1:
 MOV AH,2
 INT 21H
 ADD DX,1
              : INCREMENT +1
 LOOP L1
 MOV AH,4CH
              :TO EXIT THE REGISTER
 INT 21H
 MAIN ENDP
 END MAIN
F1=Help
                                                       Line:13
                                                                  Co1:28
C:\>W61.EXE
0123456789
C:\>EDIT W61.ASM
C:\>EDIT W62.ASM
C:N>MASM_W62.ASM;
Microsoft (R) Macro Assembler Version 5.00
Copyright (C) Microsoft Corp 1981-1985, 1987. All rights reserved.
 51720 + 464824 Bytes symbol space free
     0 Warning Errors
     O Severe Errors
C:\>LINK W62.OBJ;
Microsoft (R) Overlay Linker Version 3.60
Copyright (C) Microsoft Corp 1983-1987. All rights reserved.
C:\>W62.EXE
ABCDEFGHIJKLMNOPORSTUWXYZ
C:\>_
```

## 3. Using LOOP: Program to print a to z.

```
File Edit Search View Options Help
                                 C:NW63.ASM
 DOSSEG
 .MODEL SMALL :MODEL DIRECTIVE
 .STACK 100H
              :STACK DIRECTIVE
 .DATA
              : VARIABLE DECLERATION
 .CODE
              :CODE SPACE
 MAIN PROC
 MOV CX,26
              :LOOP RUN 26 TIMES
 MOV DX,97
              :ASCII CODE OF a
 L1:
 MOV AH,2
 INT 21H
 ADD DX,1
              : INCREMENT +1
 LOOP L1
 MOV AH,4CH
              :TO EXIT THE REGISTER
 INT 21H
 MAIN ENDP
 END MAIN
F1=Help
                                                       Line:1
                                                                 Col:1
C:\>EDIT_W63.ASM
C:N>MASM_W63.ASM;
Microsoft (R) Macro Assembler Version 5.00
Copyright (C) Microsoft Corp 1981-1985, 1987. All rights reserved.
 51720 + 464824 Bytes symbol space free
     0 Warning Errors
     O Severe Errors
C:\>LINK W63.0BJ;
Microsoft (R) Overlay Linker Version 3.60
Copyright (C) Microsoft Corp 1983-1987. All rights reserved.
C:\>W63.EXE
abcdefghijklmnopgrstuvwxyz
C:\>_
```

### 4. Practice of AND

```
File Edit Search View Options Help
                                 C:NW64.ASM
 DOSSEG
 .MODEL SMALL :MODEL DIRECTIVE
              :STACK DIRECTIVE
 .STACK 100H
              : UARIABLE DECLERATION
 .DATA
 .CODE
              :CODE SPACE
 MAIN PROC
 MOV BL, 101B
 AND BL,110B
 ADD BL,48
 MOU DL,BL
 MOV AH,2
 INT 21H
 MOU AH,4CH :TO EXIT THE REGISTER
 INT 21H
 MAIN ENDP
 END MAIN
                                                     Line:1
F1=Help
                                                                 Col:1
C:\>EDIT W64.ASM
C:\>MASM_W64.ASM;
Microsoft (R) Macro Assembler Version 5.00
Copyright (C) Microsoft Corp 1981-1985, 1987. All rights reserved.
 51720 + 464824 Bytes symbol space free
     0 Warning Errors
     O Severe Errors
C:\>LINK W64.OBJ;
Microsoft (R) Overlay Linker Version 3.60
Copyright (C) Microsoft Corp 1983–1987. All rights reserved.
C:\>\\64.EXE
C:\>
```

### **Practice of OR**

```
File Edit Search View Options Help
                                 C:NW65.ASM
 DOSSEG
 MODEL SMALL : MODEL DIRECTIVE
 .STACK 100H
              :STACK DIRECTIVE
 .DATA
              : UARIABLE DECLERATION
 .CODE
              :CODE SPACE
 MAIN PROC
 MOU BL, 101B
 OR BL,110B
 ADD BL,48
 MOU DL,BL
 MOV AH,2
 INT 21H
 MOV AH,4CH :TO EXIT THE REGISTER
 INT 21H
 MAIN ENDP
 END MAIN
F1=Help
                                                    Line:1 Col:1
C:\>EDIT W65.ASM
C:\>MASM_W65.ASM;
Microsoft (R) Macro Assembler Version 5.00
Copyright (C) Microsoft Corp 1981-1985, 1987. All rights reserved.
 51720 + 464824 Bytes symbol space free
     0 Warning Errors
     O Severe Errors
C:\>LINK W65.OBJ;
Microsoft (R) Overlay Linker Version 3.60
Copyright (C) Microsoft Corp 1983–1987. All rights reserved.
C:\>W65.EXE
```

### **Practice of XOR**

```
Mile Ddit Search View Options Help
                                 C:NW66.ASM
 DOSSEG
 .MODEL SMALL :MODEL DIRECTIVE
 .STACK 100H
              :STACK DIRECTIVE
               : UARIABLE DECLERATION
 .DATA
 .CODE
              CODE SPACE
 MAIN PROC
 MOV BL, 101B
 XOR BL,110B
 ADD BL,48
 MOV DL,BL
 MOV AH,2
 INT 21H
 MOU AH, 4CH :TO EXIT THE REGISTER
 INT 21H
 MAIN ENDP
 END MAIN
Commands for manipulating files
C:N>EDIT W66.ASM
C:N>MASM_W66.ASM;
Microsoft (R) Macro Assembler Version 5.00
Copyright (C) Microsoft Corp 1981-1985, 1987. All rights reserved.
 51720 + 464824 Bytes symbol space free
     0 Warning Errors
     O Severe Errors
C:N>LINK W66.OBJ;
Microsoft (R) Overlay Linker Version 3.60
Copyright (C) Microsoft Corp 1983-1987. All rights reserved.
C:\>W66.EXE
C:\>
```

## 5. Your code as discussed in today class

```
File Edit Search View Options Help
                                    C:NW67.ASM
 DOSSEG
 .MODEL SMALL :MODEL DIRECTIVE
 .STACK 100H
               :STACK DIRECTIVE
 .DATA
               : UARIABLE DECLERATION
 .CODE
               :CODE SPACE
 MAIN PROC
 MOV BL, 101B
 MOV CX,6
 L1:
 AND BL,110B
 MOV DL.BL
 ADD DX,1
 ADD DX,48
 MOV AH,2
 INT 21H
 LOOP L1
 MOV AH,4CH :TO EXIT THE REGISTER
 INT 21H
MAIN ENDP
Commands for manipulating files
C:N>EDIT W67.ASM
C:N>MASM_W67.ASM;
Microsoft (R) Macro Assembler Version 5.00
Copyright (C) Microsoft Corp 1981-1985, 1987. All rights reserved.
 51720 + 464824 Bytes symbol space free
      0 Warning Errors
      O Severe Errors
C:N>LINK W67.OBJ;
Microsoft (R) Overlay Linker Version 3.60
Copyright (C) Microsoft Corp 1983-1987. All rights reserved.
C:\>W67.EXE
555555
C:\>_
```