

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#exit
Router#
SYS-5-CONFIG_I: Configured from console by console
show ip interface brief
Interface      IP-Address      OK? Method Status        Protocol
FastEthernet0/0 unassigned      YES unset  administratively down down
FastEthernet0/1 unassigned      YES unset  administratively down down
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface fastethernet 0/0
Router(config-if)#ip address 90.30.30.10 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
exit
Router(config)#exit
Router#
SYS-5-CONFIG_I: Configured from console by console
show ip interface brief
      ^
Invalid input detected at '^' marker.
Router#show ip interface brief
Interface      IP-Address      OK? Method Status        Protocol
FastEthernet0/0 90.30.30.10     YES manual up          down
FastEthernet0/1 unassigned      YES unset  administratively down down
Router#
LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router#show ip interface brief
Interface      IP-Address      OK? Method Status        Protocol
FastEthernet0/0 90.30.30.10     YES manual up          up
FastEthernet0/1 unassigned      YES unset  administratively down down
Router#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
```

```

Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
>xit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
show up interface brief
^
% Invalid input detected at '^' marker.

Router#show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 90.30.30.10     YES manual up        down
FastEthernet0/1 unassigned      YES unset  administratively down down
Router#
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router#show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 90.30.30.10     YES manual up        up
FastEthernet0/1 unassigned      YES unset  administratively down down
Router#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface fastethernet 0/1
Router(config-if)#ip address 130.125.125.30 255.255.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
>xit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
show up interface brief
^
% Invalid input detected at '^' marker.

Router#show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
FastEthernet0/0 90.30.30.10     YES manual up        up
FastEthernet0/1 130.125.125.30  YES manual up        down
Router#exit

```