Setup of a Ubuntu Server Virtual Machine

First, make sure that there is a virtual machine (VM) tool (e.g., VMware Workstation) on your host machine.

Download the ISO of Ubuntu 22.04.5 live server for free. Import the ISO into the VM tool to create a new VM.

Recommended configurations for the VM:

Version	# CPU core	RAM	Storage	Firmware	Network
Ubuntu 22.04 live server	⩾2	⩾4GB	⩾20GB	BIOS	NAT

Now, start up the VM. You should see a setup interface as follows. Press Enter to start the installation.



Customize your language setting.



There should be no need to update the installer. Select "Continue without updating".



Customize your keyboard setting.



Select the standard Ubuntu Server to install.



The private network address here is automatically allocated by DHCP. Keep it as default at the current stage.



Customize your settings for the network proxy and Ubuntu mirror.



Keep the disk settings as default and continue.





Select "Continue" to begin the installation process.



Customize your settings for the username and password.



There should be no need to upgrade to Ubuntu Pro. Select "Continue".



For the SSH configuration, if you intend to connect to the VM using code editors such as VS Code, it is recommended to install the OpenSSH server and configure your authorized keys here. Alternatively, these steps can also be completed after the system is fully set up.



Check the server snaps you would like to install. It is OK to skip all of them.



Now the installation begins. Wait until the installation completes, and reboot the VM.



If you encounter the following error, just press Enter to continue the rebooting.



If the reboot succeeds, you will be instructed to enter the username and password.

Then, you are able to log in to the system. Now the Ubuntu Server VM is ready.

```
nameserver-ruc
Password:
Welcome to Ubuntu 22.04.5 LTS (GNU/Linux 5.15.0-171-generic x86_64)

 * Documentation:  https://help.ubuntu.com
 * Management:     https://landscape.canonical.com
 * Support:        https://ubuntu.com/pro

 System information as of Tue Mar  3 01:15:20 PM UTC 2026

  System load:  0.37              Processes:              240
  Usage of /:   32.0% of 9.75GB   Users logged in:        0
  Memory usage: 9%                IPv4 address for ens33: 192.168.45.139
  Swap usage:   0%

Expanded Security Maintenance for Applications is not enabled.

177 updates can be applied immediately.
124 of these updates are standard security updates.
To see these additional updates run: apt list --upgradable

Enable ESM Apps to receive additional future security updates.
See https://ubuntu.com/esm or run: sudo pro status



The programs included with the Ubuntu system are free software;
the exact distribution terms for each program are described in the
individual files in /usr/share/doc/*/copyright.

Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by
applicable law.

To run a command as administrator (user "root"), use "sudo <command>".
See "man sudo_root" for details.

nameserver-ruc@nameserver-ruc:~$
```

By default, the system requires your password every time you run a `sudo` command. To avoid entering the password repeatedly, you can add your username to the sudo group:

1. Run the command `sudo visudo`.

2. Append a new line ` <username> ALL=(ALL) NOPASSWD: ALL` at the end of the file, where `<username>` is the username when you log in to the Ubuntu VM.

3. Save and exit: Ctrl+O -> Enter -> Ctrl+X