

Configure Anonymous Access for Azure Blob Storage

Summary:-

In this lab, you will configure anonymous access for an Azure Storage Account and Blob container. You will copy the blob URL, verify that anonymous access is initially denied, enable blob anonymous access at the storage account level, configure the container access level, and verify that the blob can be accessed using its URL.

Let's Start:-


After completing this lab, you will be able to:

- Copy the URL of a blob.
- Verify the default anonymous access behavior.
- Enable anonymous blob access for a Storage Account.
- Configure the access level of a Blob container.
- Access a blob using its public URL.


Lab Steps:-

Step 1 – Copy the Blob URL


- Sign in to the Azure portal.
- Open your **Storage Account**.
- Navigate to **Containers**.



- Open the **data** container.




- Select an uploaded blob (for example, **01.py**).



- Copy the **Blob URL**.
- This step retrieves the unique URL used to access the blob.

Step 2 – Verify Anonymous Access is Disabled

- Open a new **Incognito/InPrivate** browser window.
- Paste the copied Blob URL into the address bar.
- Press **Enter**.




- Verify that access is denied and a message similar to **Public access is not permitted** is displayed.

- This step verifies that anonymous access is disabled by default.

Step 3 – Enable Anonymous Blob Access


- Return to the Azure portal.
- Open the **Storage Account**.
- From the left pane, select **Configuration**.




- Locate **Allow Blob anonymous access**.
- Change the setting to **Enabled**.
- Click **Save**.
- This step enables the Storage Account to allow anonymous blob access.

Step 4 – Change the Container Access Level

- From the left pane, select **Containers**.
- Open the **data** container.
- Click **Change access level**.




- Select **Blob (anonymous read access for blobs only)**.
- Click **OK**.



- This step grants anonymous read access to blobs stored in the container.

Step 5 – Verify Blob Access

- Return to the Incognito/InPrivate browser.
- Refresh the Blob URL.



- Verify that the blob is displayed or downloaded successfully.
- This step confirms that the blob is now accessible using its public URL.

Verification

Verify the following:

- The Blob URL is copied successfully.
- Anonymous access is denied before enabling the setting.
- Blob anonymous access is enabled for the Storage Account.
- The container access level is set to **Blob (anonymous read access for blobs only)**.
- The blob can be accessed successfully using its URL in a browser.