

UFW Firewall Configuration on Ubuntu EC2 - Step by Step

Step 1: Update the package list and install UFW:

```
sudo apt update  
sudo apt install ufw -y
```

Step 2: Check the current firewall status: sudo

```
ufw status
```

Step 3: Allow SSH access only from your public IP:

```
sudo ufw allow from 3.108.60.75 to any port 22 proto tcp
```

Step 4: Allow application traffic on port 8000: sudo

```
ufw allow 8000/tcp
```

Step 5: Enable the firewall:

```
sudo ufw enable
```

When prompted, type:

```
y
```

Step 6: Verify the firewall configuration: sudo

```
ufw status verbose
```

Expected Output:

```
Status: active  
22/tcp ALLOW IN 3.108.60.75  
8000/tcp ALLOW IN Anywhere  
8000/tcp (v6) ALLOW IN Anywhere (v6)
```

Verification:

```
sudo ufw status verbose
```

```
ubuntu@ip-172-31-34-169:~$ sudo apt update  
sudo apt install ufw -y  
Hit:1 http://ap-south-1.ec2.archive.ubuntu.com/ubuntu resolute InRelease  
Hit:2 http://ap-south-1.ec2.archive.ubuntu.com/ubuntu resolute-updates InRelease  
Hit:3 http://ap-south-1.ec2.archive.ubuntu.com/ubuntu resolute-backports InRelease  
Hit:4 http://security.ubuntu.com/ubuntu resolute-security InRelease  
2 packages can be upgraded. Run 'apt list --upgradable' to see them.  
ufw is already the newest version (0.36.2-9build1).  
ufw set to manually installed.  
Summary:  
  Upgrading: 0, Installing: 0, Removing: 0, Not Upgrading: 2  
ubuntu@ip-172-31-34-169:~$ sudo ufw status  
Status: inactive  
ubuntu@ip-172-31-34-169:~$ sudo ufw allow from 3.108.60.75 to any port 22 proto tcp  
Rules updated  
ubuntu@ip-172-31-34-169:~$ sudo ufw allow 8000/tcp  
Rules updated  
Rules updated (v6)  
ubuntu@ip-172-31-34-169:~$ sudo ufw allow 8000/tcp  
Skipping adding existing rule  
Skipping adding existing rule (v6)  
ubuntu@ip-172-31-34-169:~$ sudo ufw enable  
Command may disrupt existing ssh connections. Proceed with operation (y|n)? y  
Firewall is active and enabled on system startup  
ubuntu@ip-172-31-34-169:~$ sudo ufw status verbose  
Status: active  
Logging: on (low)  
Default: deny (incoming), allow (outgoing), deny (routed)  
New profiles: skip  
  
To Action From  
--  
22/tcp ALLOW IN 3.108.60.75  
8000/tcp ALLOW IN Anywhere  
8000/tcp (v6) ALLOW IN Anywhere (v6)  
  
ubuntu@ip-172-31-34-169:~$
```