

Mapping of the deliveries

Mapping is a licensed feature of SpeedWMS. It makes it possible to organize and visualize the route of the goods transport trucks in an optimal way. The visualization and calculation of routes is done by calling the Google Maps tool and therefore requires an access key to a Google account.

The principle is to represent on a map each of the delivery points registered for a load.

The delivery points simply correspond to the addresses of the various recipients of the orders attached to the load in question.

Mapping requires:

An access license for Google account, because it uses Windev's Google maps management functions (Google API) to:


- 1.Retrieve the coordinates of an address (latitude/longitude)
- 2.Retrieve the map of a defined location
- 3.Make a request (HTTP) to communicate with a Google service

Technical settings, because the tour plan provided by the delivery map calls Google Maps and Javascript to work, so you have to:

- 1.Have a Google account to obtain a Google Maps key (paid)
- 2.Allow <https://www.google.com/maps> site in default browser
- 3.Allow JavaScript in default browser

Functional settings, because it is necessary to fill in the information related to the delivery map in admin:

➤ **At the global configuration level of the Shipping module**




- **Google Maps license number:** the Google Maps license key is required for displaying the map.
- **Loading site:** corresponds to the default start and end points defined for the activity. However, it will be possible to enter one directly at the loading level
- **Top return site:** allows to signify the return on site of the truck after the round
- **Average time per delivery (mn):** allows you to define the average downtime for a delivery. Subsequently, it allows to define the departure time of each delivery point of the tour
- **Opacity / Thickness:** options allowing customization of the display of the route on the map in terms of ergonomics

➤ In the delivery map section in the loading form

From the upper part of the load management window, the user must first check the configuration of the cartography for the load.

A double click on the load gives access to its file:



Load [X] [✓] Load

Site: [SITE01] Site 01

Carrier: [DPD] DPD

Date: [10/08/2022] Code: [Load002] Description: [Loading South road]

Loading site: [SITE001 Site001 UK]

Departure date from site : [17/08/2022] A [08:00]

☐ Top site return

Average delivery time (mn) [30]

Last Position

Latitude [0.000000]

Longitude [0.000000]

Date [01/01/1900] A []

The Cartography tab allows you to edit the following information:

- Loading site
- Date and time of departure
- Site return point: allows you to indicate that the site defined will also be the carrier's final return point.
- Average time per delivery (in mins)

The lower part is linked to the last known space-time coordinates of the transporter:

- 5. Latitude
- 6. Longitude
- 7. Date and time

The user is free to enter this information as soon as he has it. This makes it possible to place the truck on the map in real time and to recalculate the transit times at the various delivery points.

If all the settings and conditions set out above are met, the user can now use the map to view and manage delivery rounds.

