

Access

- **Menu: Settings / Location / Areas**
- **Select a picking replenishment zone (type 003) → Context menu → Replenishment**

The settings apply to all picking locations within the selected area.

Main Parameters for Picking Replenishment

- 1. Picking quality**
 - **Defines the quality of items to be replenished at the picking location.**
- 2. Areas of origin for replenishment**
 - **Stock is taken from these areas.**
 - **Multiple areas can be selected with priorities.**
 - **Rule: Picking zones can only replenish from storage zones and vice versa.**
- 3. Picking expression unit**
 - **Defines the unit used for picking (e.g., pallet, box).**
 - **Converts the expression value into item stock units (SU).**
- 4. Picking capacity**
 - **Maximum quantity that can be picked (in picking expression units).**
- 5. Replenishment trigger threshold**
 - **Percentage threshold that triggers replenishment.**
- 6. Activation if needed**
 - **Enables replenishment if certain conditions are met.**
- 7. Max quantity per replenishment line**
 - **Defines the maximum quantity moved per replenishment line.**
 - **Prevents exceeding transport limits; if blank, the entire need can be moved at once.**
- 8. Replenishment SU**
 - **Specifies which stock unit (SU) to replenish.**

- **Must be managed at the item master level.**
- **Can be replenished by package, pallet, or stock support.**

9. Support

- **Determines whether to replenish the entire stock support (full pallet, bin, etc.), regardless of quantity.**

Criteria for Replenishment Quantity

These determine how much to replenish:

1. Restrict to the need

- **Replenish only the minimum quantity necessary.**

2. Necessity replenishment

- **Replenish at least one replenishment unit.**

3. Saturation of the picking

- **Always replenish the minimum needed to serve orders.**
- **Saturation only fills up to maximum picking quantity.**

⚠ Note: The first three options are mutually exclusive.

4. Limit to max picking

- **Ensures replenishment does not exceed the maximum picking limit.**

5. Nature of replenishment

- **Allows assigning a type or priority to replenishments for processing in RF (e.g., standard, manual, scheduled).**

6. Generation of transfer by forklift

- **Creates transfer forecasts.**
- **Updates media status to 03 so operators can move stock.**

Specific Sorting

- **The “Specific sorting” tab controls the order in which stock lines are offered for replenishment.**
- **Useful for prioritizing stock locations, oldest stock first, or specific zones.**

