

Topic: Configuration of Sampling Rules

Access Path: System / Receiving - Sampling

Purpose: Sampling rules define the logic for selecting items to undergo quality control upon receipt. Rules are evaluated in priority order.

1. Rule Management & Creation

- **Priority:** Rules are listed and searched in order of their assigned priority.
- **Creating a Rule:** Click the "+" (Add) button to create a new rule.
- **Rule Identification:**
 - A unique numeric ID is auto-assigned via incrementation.
 - A default title is also auto-generated but can be modified by the user.
- **Creation Methods:** A rule can be configured using one of two methods related to the sampling logic:
 - **Standard:** Uses the predefined sampling parameters and logic built into SpeedWMS (default).
 - **Free:** Allows the user to directly input a custom code/query into a dedicated field in the "Samplings Setting" tab, offering greater flexibility.

2. Rule Scope & Filters ("Settings" Tab)

Rules can be scoped to apply only under specific conditions via filters.

- **General Tab:** Apply broad filters using:
 - Item Family
 - Supplier Family
 - The rule will only trigger for items belonging to the selected categories.
- **Additional Tab:** Apply precise filters based on defined values related to:
 - Stock attributes
 - Order headers and lines
 - Article/item master data
 - Various Third Parties (e.g., specific suppliers, carriers) defined in SpeedWMS.

3. Sampling Logic Configuration ("Sampling Setting" Tab)

This tab defines *when* and *how* sampling occurs.

- **A. Trigger Method:** Defines the event that initiates sampling.
 - **Free:** User enters a custom query.
 - **Standard:** User selects from system-defined triggers:
 - **Rupture:** Defines a specific moment (e.g., time-based) to start sampling.
 - **New Item:** When an item unknown in the system enters stock.
 - **New Item in Reception:** When a new item is received into the environment.
 - **New Traceability Information:** When a new traceability element (e.g., batch, serial) is detected on an item.
 - **Full Support:** At any change of the handling unit/load carrier (e.g., pallet).
- **B. Sampling Parameters:** Defines the *details* of the sample.
 - **Quality:** The quality status/grade of the sample to be taken for control.
 - **Location:** The destination location where the sample should be deposited for inspection.
 - **Quantity:** The amount to sample. Two methods exist:
 1. **Value:** A fixed quantity is defined by the user in a dedicated field, based on a selected Stock Unit (SU).
 -  **Important:** When using a fixed value, ensure the items being sampled actually *manage* the selected Stock Unit in their master data.
 2. **Percentage:** A user-defined percentage of the total received quantity will be sampled. The sampled quantity therefore scales with the receipt size.