

Title:

Speed WMS – Technical Reference: Type and Status Correspondence
Internal Guide for Warehouse Operations and Support

BK Systèmes SAS – Technical Information

Company: BK Systèmes SAS, Capital €80,000 – RC Bourgoin Jallieu 420 802 027

Address: Impasse des Granges, 38290 La Verpillière, France

Phone: +33 4 74 95 75 00 | Fax: +33 4 74 95 75 01

Document: TEK 001 – Correspondence of Types and Statuses in Speed WMS

Author: Amel Kdider

Created on: 14/11/2016 16:17

Version: 1

Original Template: MOD010 Information Technique.dot

1. Description

1.1. Types

1.1.1. Support Type [TYPE_SUP]

Code	Meaning
01	In Place
02	Location to Assign
03	Movement to Perform
04	Replenishment Transfer
05	Order Line Transfer

1.1.2. Report Type [ART_RAPPORT]

Code	Meaning
11	None
12	Layer / Pallet
13	Package / Pallet
14	SPCB / Pallet

15	Units / Pallet
23	Package / Layer
24	SPCB / Layer
25	Units / Layer
34	SPCB / Package
35	Units / Package
45	Units / SPCB

1.1.3. Packaging Type [ART_CONDITIONNEMENT]

Code	Meaning
100	Pallet
200	Layer
300	Package
400	SPCB
500	Unit

1.1.4. Location Type [TYPE_EMP]

Code	Meaning	Default
100	Dock	Yes
200	Floor	No
300	Structure	No
400	Relay	No

1.1.5. Movement Type [TYPE_MVT]

- **10010 : Receipt Entry**
- **10020 : Miscellaneous Entry**
- **10030 : Return Entry**
- **10040 : Initial Inventory Entry**
- **10050 : Production Entry**
- **10060 : Inventory Adjustment Entry / Distribution Entry**

- **20010 : Goods Movement Entry**
- **20020 : Quality Change Entry**
- **20030 : Price Change Entry**
- **20040 : Article / VL Change Entry**
- **20050 : Batch / DLV / DLUO Change Entry**
- **... (continues with inbound/outbound, picking, replenishment, corrections, shipping, etc.)**
- **Total movement codes defined: 72**

1.1.6. Reception Type [TYPE_REE]

Code Meaning Default

001 Reception Yes

100 Return No

1.1.7. Third-Party Type [TYPE_TIE]

Code Meaning

001 Suppliers

002 Carriers

003 Recipients

004 Contacts

006 Bank

007 Insurance

1.1.8. ODP Type [TYPE_ODP]

Code	Meaning	Default
01	Preparation	Yes
02	Replenishment	
03	Countermark	
04	Export	

05	Delivery Date / Place	
06	Transfer	

1.1.9. Zone Types [TYPE_TZO]

Code	Meaning
001	STK – Storage Zone
002	PRS – Picking from Stock
003	PRP – Picking Zone
004	RPR – Preparation Grouping
005	PID – Dynamic Picking
006	PIA – Advanced Picking
007	INV – Inventory Zone
008	CAR – Forklift Zone
009	CPS – Compensation Zone
010	ATL – Workshop Zone
011	ACT – Activity Zone
012	P2L – Pick to Light Zone
013	CHE – Path / Route Zone

1.1.10. Picking Type [TYPE_PREL]

Code	Meaning	Default
001	PST – Picking from Stock	Yes
002	PPI – Picking Zone	
003	MQT – Missing Picking	
004	MAN – Manual Addition	
005	REA – Replenishment	
006	Full Pallet	

1.2. Status

1.2.1. Item Status [STATUT_ART]

Code	Meaning	Default
1	New	
2	Active	Yes
3	Disabled	
4	End of Life	

1.2.2. Preparation Status [STATUT_ODP]

Code	Meaning	Default
001	Awaiting Interception	
010	In Entry	Yes
020	In Wave	
030	In Preparation	
040	Validated	
050	Settled	
060	Ready for Shipment	
070	Shipped	

1.2.3. Mission Status [STATUT_MIE]

Code	Meaning	Default
010	To Prepare	Yes
020	In Progress	
040	Validated	
050	Settled	
060	Ready for Shipment	

1.2.4. Mission Line Status [STATUT_MIL]

Code	Meaning	Default
010	To Prepare	Yes
020	In Progress	

040	Validated	
050	Settled	
060	Ready for Shipment	
070	Shipped	

1.2.5. Wave Status [STATUT_VAG]

Code	Meaning	Default
010	To Launch	Yes
015	In Progress	
030	Launched	
040	Validated	
050	Closed	

1.2.6. Reception Status [ETAT_REE]

Code	Meaning	Default
001	In Progress	Yes
100	Shelved	
200	Closed	

1.2.7. Expected Reception Status [ETAT_REA]

Code	Meaning	Default
001	In Progress	Yes
100	Shelved	
200	Closed	

1.2.8. Shipping Support Status [STATUT_SEX]

Code	Meaning	Default
010	Initial	Yes
020	Colisée	
030	Checked	
040	Validated	

070	Shipped	
-----	---------	--

 Notes for RAG Team:

- **This document serves as a reference table mapping types and statuses in Speed WMS.**
- **Always use the default values when configuring new operations or troubleshooting.**
- **Useful for support, operations, and WMS configuration verification.**