

Key the radio, say the wake word, then your call — **one transmission, one call**. The wake word may sit anywhere in the sentence. Release the key and wait: the answer comes on the same frequency, addressed to your callsign.

FREQUENCIES ON THIS SERVER — FROM THE F10 MAP MARKERS			
Wake word		AWACS	
Tanker		Your tower	

AIR PICTURE — needs the mission data link

BOGEY DOPE

The nearest hostile group, measured from your own aircraft.

SAY "Overlord, bogey dope."
◀ Punch 1-1, this is Overlord. Bogey, bearing zero, niner, zero, thirty five miles, twenty two thousand, hot, group of two, type MiG-29.

PICTURE

The whole hostile picture, grouped, from the bullseye.

SAY "Overlord, picture."
◀ Picture: two groups. Lead group, bullseye two, seven, zero, for forty miles, twenty five thousand, two contacts, Su-27...

THREAT CHECK

Only the nearest threat. Short, for when you have no time.

SAY "Overlord, threat check."
◀ Nearest contact zero, niner, zero at thirty five miles, twenty two thousand.

ALPHA CHECK

Your own position from the bullseye. Navigation cross-check.

SAY "Overlord, Punch 1-1, alpha check bullseye."
◀ Alpha check, bullseye zero, one, zero, one hundred twenty two miles, twenty two thousand.

WHERE IS ... (only if your server enabled it)

Where another human pilot on your side is. The name goes after the phrase.

SAY "Overlord, where is Springfield 2-1?"
◀ Springfield 2 1, bullseye two, seven, zero, for forty miles, twenty two thousand, heading zero, niner, zero.

A STANDING WATCH

THREAT CIRCLE

A standing watch that moves with you. It calls out a hostile entering the circle, once each, until you cancel it.

SAY "Overlord, threat circle forty miles."
"Overlord, cancel threat circle."

◀ *Threat circle active, forty miles. ... Punch 1-1, this is Overlord. Threat, bearing zero, niner, five, twenty two miles, hot, type MiG-29.*

AIRFIELD — name a field, or say nothing for the nearest one

RUNWAY IN USE

The runway the wind favours, with that wind.

SAY "Overlord, Batumi, runway in use."

◀ *Batumi, runway in use one three, wind one three zero at one niner knots.*

ATIS

Wind, temperature, pressure and the runway, as a broadcast.

SAY "Overlord, Kobuleti ATIS."

◀ *Kobuleti information, wind two one zero at eight knots, temperature one five, QNH one zero one three, altimeter two niner niner two, runway in use two five.*

ALWAYS WORKS — no mission data needed, answers on every frequency

RADIO CHECK

Is the bot there, and does it have you on scope? Start here when something seems wrong.

SAY "Overlord, radio check."

◀ *Loud and clear, contact. / Loud and clear, but no radar contact on you.*

SMALL TALK IT ANSWERS — samples your admin can change

"say again"	Copy, say again your last transmission.
"status"	All systems nominal.
"check in"	Copy your check-in.
"request weather"	Weather is clear, visibility unrestricted. <i>(gives the real ATIS when the airfield replies are on)</i>
"request RTB"	Copy, cleared to RTB.

FROM YOU, OR FROM THE BULLSEYE

Bogey dope and **threat check** are measured from your aircraft — bearing and range are what you fly. **Picture** is from the bullseye, because it describes several groups at once.

Add the word **bullseye** to any of them to force the bullseye format: "*Overlord, bogey dope bullseye.*"

ASPECT — WHERE THE NOSE POINTS

HOT	coming at you
FLANKING	crossing, roughly 45°
BEAMING	across your nose, 90°
COLD	running away

Numbers are spoken digit by digit: "*zero niner zero*" is 090. Due north is "*three six zero*", never zero.

WHEN THE ANSWER IS "STANDBY"

"...message received, standby."	It heard you and is still working. The real answer follows.
"...standby, working other traffic."	You are over the per-pilot limit. Give it a moment; it says this once and then stays quiet until the limit clears.

NOTHING CAME BACK

- Say "**radio check**" first. It answers on every frequency and needs no mission data, so it separates "bot is down" from "wrong frequency" from "it cannot see you".
- "*Loud and clear, **but no radar contact on you***" means your name could not be matched to your aircraft: you still get answers, but from the bullseye instead of from your jet. Fix the name — see below.
- Did you say the **wake word**? Nothing without it is even listened to.
- One call per transmission. Two questions in one go get one answer at best.
- While the bot is speaking it does not hear you. Let it finish, then key up.

Your SRS name decides whether it can find your jet. Write it as CALLSIGN 1-1 | YourName — the part before the | has to match the callsign of the aircraft you are flying in DCS. Then BRAA calls are measured from your aircraft and the bot addresses you as "Punch 1-1" instead of reading your whole handle out.

IF IT MISHEARS YOU

The wake word is recognised offline by a small model. It is not your accent being judged — it simply hears some voices better than others.

- Say the wake word **first and clearly**, then pause a beat.
- Do not shout; a hot mic distorts more than it helps.
- If it keeps missing your voice, tell the server admin — the spelling it hears can be added, and that fixes it for good.