D.A.R.K.S.T.A.R. // RADIO CALLS

Key the radio, say the wake word, then your call — **one transmission, one call**. The wake word may sit anywhere in the sentence. Release the key and wait: the answer comes on the same frequency, addressed to your callsign.

FREQUENCIES ON THIS SERVER — FROM THE F10 MAP MARKERS			
Wake word	.....	**AWACS**	.....
Tanker	.....	**Your tower**	.....

AIR PICTURE — needs the mission data link

BOGEY DOPE

The nearest hostile group, measured from your own aircraft.

SAY **"Overlord, bogey dope."**

◂ *Punch 1-1, this is Overlord. Bogey, bearing zero, niner, zero, thirty five miles, twenty two thousand, hot, group of two, type MiG-29.*

PICTURE

The whole hostile picture, grouped, from the bullseye.

SAY **"Overlord, picture."**

◂ *Picture: two groups. Lead group, bullseye two, seven, zero, for forty miles, twenty five thousand, two contacts, Su-27... Groups azimuth.*

THREAT CHECK

Only the nearest threat. Short, for when you have no time.

SAY **"Overlord, threat check."**

◂ *Nearest contact zero, niner, zero at thirty five miles, twenty two thousand.*

DECLARE · SPIKE

What sits at a point, or on a bearing. **Furball** = both sides mixed, do not shoot.

SAY **"Overlord, declare bullseye zero three zero for four five."**
"Overlord, spike two seven zero."

◂ *Hostile, two contacts, twenty five thousand, fast, MiG-29. / Buddy spike, twelve miles.*

ALPHA CHECK

Your **own** position from the bullseye. Navigation cross-check.

SAY **"Overlord, Punch 1-1, alpha check bullseye."**

◂ *Alpha check, bullseye zero, one, zero, one hundred twenty two miles, twenty two thousand.*

WHERE IS … (only if your server enabled it)

Where another **human** pilot on your side is. The name goes **after** the phrase.

SAY **"Overlord, where is Springfield 2-1?"**

◂ *Springfield 2 1, bullseye two, seven, zero, for forty miles, twenty two thousand, heading zero, niner, zero.*

A STANDING WATCH

THREAT CIRCLE
A standing watch that moves with you. It calls out a hostile entering the circle, once each, until you cancel it.

SAY **"Overlord, threat circle forty miles."**
"Overlord, cancel threat circle."

◂ *Threat circle active, forty miles. … Punch 1-1, this is Overlord. Threat, bearing zero, niner, five, twenty two miles, hot, type MiG-29.*

AIRFIELD — name a field, or say nothing for the nearest one

RUNWAY IN USE
The runway the wind favours, with that wind.

SAY **"Overlord, Batumi, runway in use."**

◂ *Batumi, runway in use one three, wind one three zero at one niner knots.*

ATIS
Wind, temperature, pressure and the runway, as a broadcast.

SAY **"Overlord, Kobuleti ATIS."**

◂ *Kobuleti information, wind two one zero at eight knots, temperature one five, QNH one zero one three, altimeter two niner niner two, runway in use two five.*

DIVERT
Somewhere to land. No TACAN or tower frequency — the mission data has neither.

SAY **"Overlord, vector to nearest."**

◂ *Divert options: Kutaisi, bearing two, four, five, thirty eight miles, field elevation 150 feet. Senaki, bearing three, zero, zero, fifty two miles.*

ALWAYS WORKS — no mission data needed, answers on every frequency

RADIO CHECK
Is the bot there, and does it have you on scope? Start here when something seems wrong.

SAY **"Overlord, radio check."**

◂ *Loud and clear, contact. / Loud and clear, but no radar contact on you.*

ON STATION — and asking for a repeat

"say again"	The last thing you were told, again. Any call, not just a tactical one.
"checking in"	Punch 1-1, radar contact, cleared into the area.
"checking out"	Radar service terminated. Also ends your threat circle.

SMALL TALK IT ANSWERS — samples your admin can change

"status"	All systems nominal.
"request weather"	Weather is clear, visibility unrestricted. *(gives the real ATIS when the airfield replies are on)*
"request RTB"	Copy, cleared to RTB.

D.A.R.K.S.T.A.R. // THE ANSWERS

FROM YOU, OR FROM THE BULLSEYE

Bogey dope and **threat check** are measured from your aircraft — bearing and range are what you fly. **Picture** is from the bullseye, because it describes several groups at once.

Add the word **`bullseye`** to any of them to force the bullseye format: "*Overlord, bogey dope bullseye.*"

ASPECT — WHERE THE NOSE POINTS

HOT	coming at you
FLANKING	crossing, roughly 45°
BEAMING	across your nose, 90°
COLD	running away

Numbers are spoken digit by digit: "*zero niner zero*" is 090. Due north is "*three six zero*", never zero.

WHEN THE ANSWER IS "STANDBY"

"...message received, standby."	It heard you and is still working. The real answer follows.
"...standby, working other traffic."	You are over the per-pilot limit. Give it a moment; it says this once and then stays quiet until the limit clears.

NOTHING CAME BACK

- Say **"radio check"** first. It answers on every frequency and needs no mission data, so it separates "bot is down" from "wrong frequency" from "it cannot see you".
- "*Loud and clear, **but no radar contact on you***" means your name could not be matched to your aircraft: you still get answers, but from the bullseye instead of from your jet. Fix the name — see below.
- Did you say the **wake word**? Nothing without it is even listened to.
- One call per transmission. Two questions in one go get one answer at best.
- While the bot is speaking it does not hear you. Let it finish, then key up.
- **Still not understood?** Open the **comms menu** (`\` by default), then **`F10 → Darkstar`**. Usually **F1**; your call is read back first, so the others hear both sides.

> **Your SRS name decides whether it can find your jet.** Write it as `CALLSIGN 1-1 | YourName` — the part before the `|` has to match the callsign of the aircraft you are flying in DCS. Then BRAA calls are measured from your aircraft and the bot addresses you as "Punch 1-1" instead of reading your whole handle out.

IF IT MISHEARS YOU

The wake word is recognised offline by a small model. It is not your accent being judged — it simply hears some voices better than others.

- Say the wake word **first and clearly**, then pause a beat.
- Do not shout; a hot mic distorts more than it helps.
- If it keeps missing your voice, tell the server admin — the spelling it hears can be added, and that fixes it for good.