Tiering inactive data from your first cluster to Google Cloud Storage

Cloud Tiering

Ben Cammett, Aksel Davis
October 07, 2020

This PDF was generated from https://docs.netapp.com/us-en/cloud-tiering/task_tiering_google.html on March 06, 2021. Always check docs.netapp.com for the latest.

Table of Contents

Tiering inactive data from your first cluster to Google Cloud Storage 1

Tiering inactive data from your first cluster to Google Cloud Storage

After you prepare your Google Cloud environment, just log in to Cloud Tiering and start tiering inactive data from your first cluster.

What you'll need

- To discover the cluster, you'll need the following:
  - The cluster management IP address.
  - The user name and password of an ONTAP account that has administrator-level privileges.

    The Service Connector uses this account to send API operations to the ONTAP cluster.
- To deploy the Service Connector in GCP, you'll need the following:
  - A Google account that has the required permissions to deploy the Service Connector virtual machine.
  - The project, region, VPC, and subnet in which the Service Connector will reside.
  - A service account that includes the permissions defined in the Service Connector policy for GCP.
- To set up tiering to Google Cloud Storage, you'll need storage access keys for a service account that has the Storage Admin role.

If you haven't met these requirements, see Preparing to tier data to Google Cloud Storage.

Steps

1. Log in to NetApp Cloud Central.
2. Select the Cloud Tiering service.
3. Click **Let's Start, Discover Your First Cluster**.
4. Complete the steps on the **Discover Cluster** page:
   a. Enter the cluster management IP address and the user name and password of an account that has administrator-level privileges.



b. Click **Discover Cluster**.

   If you already have an existing Service Connector, then Cloud Tiering automatically attempts to use that Service Connector. Cloud Tiering moves on to the next step, if any existing Service Connector has connectivity to the cluster.

c. If Cloud Tiering prompts you to create a Service Connector, click **Create your first Service Connector**.

   If you have an existing Service Connector and Cloud Tiering can't use it, then you'll need to do one of two things:

   - Click **Add Service Connector** to create a new Service Connector.
   - Check the status and connectivity of any existing Service Connectors and then try to discover the cluster again.

d. If you clicked the button to create a Service Connector, follow the prompts to deploy it in GCP:

   - **Select Provider**: Select **Google Cloud Platform** as the target location for the Service Connector.

     When prompted, sign in and accept the permissions request from Google. The form is owned and hosted by Google. Your credentials are not provided to NetApp.

   - **Basic Settings**: Enter a name for the virtual machine, select a project, and then select a service account that includes the permissions defined in the Service Connector policy for GCP.
   - **Location**: Specify networking for the virtual machine—a region, zone, VPC, and subnet, and then choose whether you want to assign a public IP address and specify an HTTP proxy for outbound connectivity.

     Remember, the Service Connector must have a constant connection to the ONTAP cluster and a

constant internet connection to the Cloud Tiering service.

- **Firewall Policy**: Select **Create a new firewall policy** so Cloud Tiering can create the security group, or select an existing firewall policy. Then click **Go**.

  The firewall policy that Cloud Tiering creates allows inbound HTTP, HTTPS, and SSH connectivity. It has open outbound connectivity.

  Leave the page open until the deployment is complete.

e. Back on the Discover Cluster page, select the Service Connector that you just created.

5. Complete the steps on the **Tiering Setup** page:

   a. **Bucket**: Add a new Google Cloud Storage bucket or select an existing bucket and click **Continue**.

   b. **Storage Class**: Select the storage class that you want to use for the tiered data and click **Continue**.

   c. **Credentials**: Enter the storage access key and secret key for a service account that has the Storage Admin role.

   d. **Cluster Network**: Select the IPspace that ONTAP should use to connect to object storage and click **Continue**.

      Selecting the correct IPspace ensures that Cloud Tiering can set up a connection from ONTAP to your cloud provider's object storage.

      If you haven't reviewed requirements for the IPspace and the associated intercluster LIFs, see ONTAP cluster requirements.

6. Click **Continue** to select the volumes that you want to tier.

7. For each volume, click the icon, select a tiering policy, optionally adjust the cooling days, and click **Apply**.

   Learn about volume tiering policies and cooling days.



8. When you're done, click **Close**.

Result

You've successfully set up data tiering from volumes on the cluster to Google Cloud object storage.

What's next?

Be sure to subscribe to the Cloud Tiering service from the GCP Marketplace.

You can also add additional clusters or review information about the active and inactive data on the cluster. For

details, see Managing data tiering from your clusters.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.