Setting up and adding AWS accounts to Cloud Manager

Cloud Manager 3.7

Ben Cammett
January 03, 2020

This PDF was generated from https://docs.netapp.com/us-en/occm37/task_adding_aws_accounts.html on April 25, 2020. Always check docs.netapp.com for the latest.

Table of Contents

Setting up and adding AWS accounts to Cloud Manager 1
Granting permissions by providing AWS keys 1
Granting permissions by assuming IAM roles in other accounts 2
Adding AWS accounts to Cloud Manager 2

Setting up and adding AWS accounts to Cloud Manager

If you want to deploy Cloud Volumes ONTAP in different AWS accounts, then you need to provide the required permissions and add the details to Cloud Manager. How you provide the permissions depends on whether you want to provide Cloud Manager with AWS keys or the ARN of a role in a trusted account.

> When you deploy Cloud Manager from Cloud Central, Cloud Manager automatically adds the AWS account in which you deployed Cloud Manager. An initial account is not added if you manually installed the Cloud Manager software on an existing system. Learn about AWS accounts and permissions.

Choices

- Granting permissions by providing AWS keys
- Granting permissions by assuming IAM roles in other accounts

Granting permissions by providing AWS keys

If you want to provide Cloud Manager with AWS keys for an IAM user, then you need to grant the required permissions to that user. The Cloud Manager IAM policy defines the AWS actions and resources that Cloud Manager is allowed to use.

Steps

1. Download the Cloud Manager IAM policy from the Cloud Manager Policies page.
2. From the IAM console, create your own policy by copying and pasting the text from the Cloud Manager IAM policy.

   AWS Documentation: Creating IAM Policies

3. Attach the policy to an IAM role or an IAM user.
   - AWS Documentation: Creating IAM Roles
   - AWS Documentation: Adding and Removing IAM Policies

Result

The account now has the required permissions. You can now add it to Cloud Manager.

Granting permissions by assuming IAM roles in other accounts

You can set up a trust relationship between the source AWS account in which you deployed the Cloud Manager instance and other AWS accounts by using IAM roles. You would then provide Cloud Manager with the ARN of the IAM roles from the trusted accounts.

Steps

1. Go to the target account where you want to deploy Cloud Volumes ONTAP and create an IAM role by selecting **Another AWS account**.

   Be sure to do the following:

   - Enter the ID of the account where the Cloud Manager instance resides.
   - Attach the Cloud Manager IAM policy, which is available from the Cloud Manager Policies page.

2. Go to the source account where the Cloud Manager instance resides and select the IAM role that is attached to the instance.

   a. Click **Trust Relationships** > **Edit trust relationship**.

   b. Add the "sts:AssumeRole" action and the ARN of the role that you created in the target account.

   Example

```
{
 "Version": "2012-10-17",
 "Statement": {
   "Effect": "Allow",
   "Action": "sts:AssumeRole",
   "Resource": "arn:aws:iam::ACCOUNT-B-ID:role/ACCOUNT-B-ROLENAME"
}
}
```

Result

The account now has the required permissions. You can now add it to Cloud Manager.

Adding AWS accounts to Cloud Manager

After you provide an AWS account with the required permissions, you can add the account to Cloud Manager. This enables you to launch Cloud Volumes ONTAP systems in that account.

Steps

1. In the upper right of the Cloud Manager console, click the Settings icon, and select **Cloud Provider & Support Accounts**.



2. Click **Add New Account** and select **AWS**.
3. Choose whether you want to provide AWS keys or the ARN of a trusted IAM role.
4. Confirm that the policy requirements have been met and then click **Create Account**.

Result

You can now switch to another account from the Details and Credentials page when creating a new working environment:



Copyright Information

Copyright © 2019–2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.