用于在集群模式 Data ONTAP 中 Snap Creator 用建角色的命令行界面命令

Snap Creator Framework

NetApp
October 27, 2021

This PDF was generated from https://docs.netapp.com/zh-cn/snap-creator-framework/installation/reference_cli_command_for_creating_cluster_roles.html on October 27, 2021. Always check docs.netapp.com for the latest.

目□

用于在集群模式 Data ONTAP 中□ Snap Creator 用□□建角色的命令行界面命令 1
用于□建集群角色的 CLI 命令 1
用于□建 SVM 角色的 CLI 命令 6

用于在集群模式 Data ONTAP 中□ Snap Creator 用□□建角色的命令行界面命令

在集群模式 Data ONTAP 中□建 Snap Creator 用□□，必□□行各□命令□新的集群用□或 SVM 用□□建一个角色。

用于□建集群角色的 CLI 命令

下表列出了□新集群用□□建角色所需的命令。

命令目□名称	要□行的命令
cluster identity show	role create -role CRBAC_New -cmddirname "cluster identity show" -vserver clus3240rre
事件	role create -role CRBAC_New -cmddirname "event" -vserver clus3240rre
事件配置	role create -role CRBAC_New -cmddirname "event config" -vserver clus3240rre
事件目□	role create -role CRBAC_New -cmddirname "event destination" -vserver clus3240rre
事件日志	role create -role CRBAC_New -cmddirname "event log" -vserver clus3240rre
事件□件□史□□	role create -role CRBAC_New -cmddirname "event mailhistory" -vserver clus3240rre
事件路由	role create -role CRBAC_New -cmddirname "event route" -vserver clus3240rre
事件□史□□	role create -role CRBAC_New -cmddirname "event snmphistory" -vserver clus3240rre
事件状□	role create -role CRBAC_New -cmddirname "event status" -vserver clus3240rre
LUN 注□	role create -role CRBAC_New -cmddirname "lun comment" -vserver clus3240rre
□建 LUN	role create -role CRBAC_New -cmddirname "lun create" -vserver clus3240rre

命令目□名称	要□行的命令
LUN □除	role create -role CRBAC_New -cmddirname "lun delete" -vserver clus3240rre
LUN 几何□□	role create -role CRBAC_New -cmddirname "lun geometer" -vserver clus3240rre
lun igroup add	role create -role CRBAC_New -cmddirname "lun igroup add" -vserver clus3240rre
lun igroup create	role create -role CRBAC_New -cmddirname "lun igroup create" -vserver clus3240rre
已□置 LUN igroup	role create -role CRBAC_New -cmddirname "lun igroup set" -vserver clus3240rre
lun igroup show	role create -role CRBAC_New -cmddirname "lun igroup show" -vserver clus3240rre
LUN 映射	role create -role CRBAC_New -cmddirname "lun map" -vserver clus3240rre
lun mapping show	role create -role CRBAC_New -cmddirname "lun mapping show" -vserver clus3240rre
修改 LUN	role create -role CRBAC_New -cmddirname "lun modify" -vserver clus3240rre
LUN 移□	role create -role CRBAC_New -cmddirname "lun move" -vserver clus3240rre
LUN 脱机	role create -role CRBAC_New -cmddirname "lun offline" -vserver clus3240rre
LUN □机	role create -role CRBAC_New -cmddirname "lun online" -vserver clus3240rre
□整 LUN 大小	role create -role CRBAC_New -cmddirname "lun resize" -vserver clus3240rre
lun show	role create -role CRBAC_New -cmddirname "lun show" -vserver clus3240rre
LUN 取消映射	role create -role CRBAC_New -cmddirname "lun unmap" -vserver clus3240rre

命令目□名称	要□行的命令
网□	role create -role CRBAC_New -cmddirname "network" -vserver clus3240rre
network fcp adapter show	role create -role CRBAC_New -cmddirname "network fcp adapter show" -vserver clus3240rre
network interface show	role create -role CRBAC_New -cmddirname "network interface show" -vserver clus3240rre
security login role show	role create -role CRBAC_New -cmddirname "security login role show" -vserver clus3240rre
security login show	role create -role CRBAC_New -cmddirname "security login show" -vserver clus3240rre
SnapMirror	role create -role CRBAC_New -cmddirname "snapmirror" -vserver clus3240rre
存□聚合	role create -role CRBAC_New -cmddirname "storage aggregate" -vserver clus3240rre
system license show	role create -role CRBAC_New -cmddirname "system license show" -vserver clus3240rre
系□□点	role create -role CRBAC_New -cmddirname "system node" -vserver clus3240rre
系□□点 AutoSupport	role create -role CRBAC_New -cmddirname "system node AutoSupport "-vserver clus3240rre
系□□点 AutoSupport □用	role create -role CRBAC_New -cmddirname "system node AutoSupport invoke" -vserver clus3240rre
system node show	role create -role CRBAC_New -cmddirname "system node show" -vserver clus3240rre
系□□点□行	role create -role CRBAC_New -cmddirname "system node run" -vserver clus3240rre
系□服□ NDMP	role create -role CRBAC_New -cmddirname "system services ndmp" -vserver clus3240rre
version	role create -role CRBAC_New -cmddirname "version" -vserver clus3240rre

命令目□名称	要□行的命令
version	security login role create -role bainew1 -vserver SnapCreator -cmddirname "version" -access readonly
□建 SVM □出策略□□	role create -role CRBAC_New -cmddirname "vserver export-policy rule create" -vserver clus3240rre
vserver export-policy rule show	role create -role CRBAC_New -cmddirname "vserver export-policy rule show" -vserver clus3240rre
vserver export-policy show	role create -role CRBAC_New -cmddirname "vserver export-policy show" -vserver clus3240rre
Vserver FCP	role create -role CRBAC_New -cmddirname "vserver fcp" -vserver snapcreator -vserver clus3240rre
vserver fcp initiator show	role create -role CRBAC_New -cmddirname "vserver fcp initiator show" -vserver clus3240rre
vserver fcp show	role create -role CRBAC_New -cmddirname "vserver fcp show" -vserver clus3240rre
SVM FCP 状□	role create -role CRBAC_New -cmddirname "vserver fcp status" -vserver clus3240rre
vserver iscsi connection show	role create -role CRBAC_New -cmddirname "vserver iscsi connection show" -vserver clus3240rre
SVM iSCSI	role create -role CRBAC_New -cmddirname "vserver iscsi" -vserver Snapcreator -vserver clus3240rre
添加 SVM iSCSI 接口□□列表	role create -role CRBAC_New -cmddirname "vserver iscsi interface accesslist add" -vserver clus3240rre
vserver iscsi interface accesslist show	role create -role CRBAC_New -cmddirname "vserver iscsi interface accesslist show" -vserver clus3240rre
SVM iSCSI □点名称	role create -role CRBAC_New -cmddirname "vserver iscsi nodename " -vserver clus3240rre
vserver iscsi session show	role create -role CRBAC_New -cmddirname "vserver iscsi session" show -vserver clus3240rre
vserver iscsi show	role create -role CRBAC_New -cmddirname "vserver iscsi show" -vserver clus3240rre

命令目□名称	要□行的命令
SVM iSCSI 状□	role create -role CRBAC_New -cmddirname "vserver iscsi status" -vserver clus3240rre
Vserver NFS	role create -role CRBAC_New -cmddirname "vserver nfs" -vserver Snapcreator -vserver clus3240rre
Vserver NFS 状□	role create -role CRBAC_New -cmddirname "vserver nfs status" -vserver clus3240rre
SVM □□	role create -role CRBAC_New -cmddirname "vserver options" -vserver clus3240rre
vserver services unix-group create	role create -role CRBAC_New -cmddirname "vserver services name-service unix-group create" -vserver clus3240rre
vserver services unix-user create	role create -role CRBAC_New -cmddirname "vserver services name-service unix-user create" -vserver clus3240rre
vserver services unix-group show	role create -role CRBAC_New -cmddirname "vserver services name-service unix-group show" -vserver clus3240rre
vserver services unix-user show	role create -role CRBAC_New -cmddirname "vserver services name-service unix-user show" -vserver clus3240rre
vserver show	role create -role CRBAC_New -cmddirname "vserver show" -vserver clus3240rre
卷自□□整大小	role create -role CRBAC_New -cmddirname "volume autosize" -vserver clus3240rre
□建卷克隆	role create -role CRBAC_New -cmddirname "volume clone create" -vserver clus3240rre
卷□建	role create -role CRBAC_New -cmddirname "volume create" -vserver clus3240rre
卷□□	role create -role CRBAC_New -cmddirname "volume destroy" -vserver clus3240rre
卷效率□□	role create -role CRBAC_New -cmddirname "volume efficiency off" -vserver clus3240rre

命令目□名称	要□行的命令
卷效率打□	role create -role CRBAC_New -cmddirname "volume efficiency on" -vserver clus3240rre
volume efficiency show	role create -role CRBAC_New -cmddirname "volume efficiency show" -vserver clus3240rre
卷效率□□	role create -role CRBAC_New -cmddirname "volume efficiency start" -vserver clus3240rre
卷文件	role create -role CRBAC_New -cmddirname "volume file" -vserver clus3240rre
□建卷文件克隆	role create -role CRBAC_New -cmddirname "volume file clone create" -vserver clus3240rre
volume file show-disk-usage	role create -role bainew1 -vserver SnapCreator -cmddirname "volume file show-disk-usage" -access all
卷修改	role create -role CRBAC_New -cmddirname "volume modify" -vserver clus3240rre
卷脱机	role create -role CRBAC_New -cmddirname "volume offline" -vserver clus3240rre
volume show	role create -role CRBAC_New -cmddirname "volume show" -vserver clus3240rre
卷大小	role create -role CRBAC_New -cmddirname "volume size" -vserver clus3240rre
□建卷快照	role create -role CRBAC_New -cmddirname "volume snapshot create" -vserver clus3240rre
卷卸□	role create -role CRBAC_New -cmddirname "volume unmount "-vserver clus3240rre

用于□建 SVM 角色的 CLI 命令

下表列出了□新 SVM 用□□建角色所需的命令。

命令目□名称	要□行的命令
添加用□	role create -role vserrbacrole_new -cmddirname "adduser" -vserver Snapcreator

命令目□名称	要□行的命令
event generate-autosupport-log	role create -role vserrbacrole_new -cmddirname "event generate-autosupport-log" -vserver Snapcreator
LUN 注□	role create -role vserrbacrole_new -cmddirname "lun comment" -vserver Snapcreator
□建 LUN	role create -role vserrbacrole_new -cmddirname "lun create" -vserver Snapcreator
LUN □除	role create -role vserrbacrole_new -cmddirname "lun delete" -vserver Snapcreator
LUN 几何□□	role create -role vserrbacrole_new -cmddirname "lun geometer" -vserver Snapcreator
lun igroup add	role create -role vserrbacrole_new -cmddirname "lun igroup add" -vserver Snapcreator
lun igroup create	role create -role vserrbacrole_new -cmddirname "lun igroup create" -vserver Snapcreator
已□置 LUN igroup	role create -role vserrbacrole_new -cmddirname "lun igroup set" -vserver Snapcreator
lun igroup show	role create -role vserrbacrole_new -cmddirname "lun igroup show" -vserver Snapcreator
LUN 映射	role create -role vserrbacrole_new -cmddirname "lun map" -vserver Snapcreator
lun mapping show	role create -role vserrbacrole_new -cmddirname "lun mapping show" -vserver Snapcreator
修改 LUN	role create -role vserrbacrole_new -cmddirname "lun modify" -vserver Snapcreator
LUN 移□	role create -role vserrbacrole_new -cmddirname "lun move" -vserver Snapcreator
LUN 脱机	role create -role vserrbacrole_new -cmddirname "lun offline" -vserver Snapcreator
LUN □机	role create -role vserrbacrole_new -cmddirname "lun online" -vserver Snapcreator

命令目□名称	要□行的命令
□整 LUN 大小	role create -role vserrbacrole_new -cmddirname "lun resize" -vserver Snapcreator
lun show	role create -role vserrbacrole_new -cmddirname "lun show" -vserver Snapcreator
LUN 取消映射	role create -role vserrbacrole_new -cmddirname "lun unmap" -vserver Snapcreator
网□	role create -role vserrbacrole_new -cmddirname "network" -vserver SnapCreator
网□□接	role create -role vserrbacrole_new -cmddirname "network connections" -vserver SnapCreator
网□□接□于活□状□	role create -role vserrbacrole_new -cmddirname "network connections active" -vserver SnapCreator
network connections listening show	role create -role vserrbacrole_new -cmddirname "network connections listening show" -vserver SnapCreator
网□接口	role create -role vserrbacrole_new -cmddirname "network interface" -vserver SnapCreator
网□路由□	role create -role vserrbacrole_new -cmddirname "network routing-groups" -vserver SnapCreator
restore-file	role create -role vserrbacrole_new -cmddirname "restore-file" -vserver Snapcreator
SnapMirror	role create -role vserrbacrole_new -cmddirname "snapmirror" -vserver SnapCreator
version	role create -role vserrbacrole_new -cmddirname "version" -vserver Snapcreator
volume	role create -role vserrbacrole_new -cmddirname "volume"
卷自□□整大小	role create -role vserrbacrole_new -cmddirname "volume autosize" -vserver Snapcreator
卷克隆	role create -role vserrbacrole_new -cmddirname "volume clone" -vserver Snapcreator

命令目□名称	要□行的命令
□建卷克隆	role create -role vserrbacrole_new -cmddirname "volume clone create" -vserver Snapcreator
卷□建	role create -role vserrbacrole_new -cmddirname "volume create" -vserver Snapcreator
卷□□	role create -role vserrbacrole_new -cmddirname "volume destroy" -vserver Snapcreator
卷效率□□	role create -role vserrbacrole_new -cmddirname "volume efficiency off" -vserver Snapcreator
卷效率打□	role create -role vserrbacrole_new -cmddirname "volume efficiency on" -vserver Snapcreator
卷效率□□	role create -role vserrbacrole_new -cmddirname "volume efficiency start" -vserver Snapcreator
volume efficiency show	role create -role vserrbacrole_new -cmddirname "volume efficiency show" -vserver Snapcreator
卷文件	role create -role vserrbacrole_new -cmddirname "volume file" -vserver Snapcreator
卷文件克隆	role create -role vserrbacrole_new -cmddirname "volume file clone" -vserver Snapcreator
□建卷文件克隆	role create -role vserrbacrole_new -cmddirname "volume file clone create" -vserver Snapcreator
卷修改	role create -role vserrbacrole_new -cmddirname "volume modify" -vserver Snapcreator
卷挂□	role create -role vserrbacrole_new -cmddirname "volume mount" -vserver Snapcreator
卷脱机	role create -role vserrbacrole_new -cmddirname "volume offline" -vserver Snapcreator
volume show	role create -role vserrbacrole_new -cmddirname "volume show" -vserver Snapcreator
卷大小	role create -role vserrbacrole_new -cmddirname "volume size" -vserver Snapcreator

命令目□名称	要□行的命令
□建卷快照	role create -role vserrbacrole_new -cmddirname "volume snapshot create" -vserver Snapcreator
卷快照□除	role create -role vserrbacrole_new -cmddirname "volume snapshot delete" -vserver Snapcreator
卷快照□原	role create -role vserrbacrole_new -cmddirname "volume snapshot restore" -vserver Snapcreator
卷卸□	role create -role vserrbacrole_new -cmddirname "volume unmount " -vserver Snapcreator
vserver export-policy rule show	role create -role vserrbacrole_new -cmddirname "vserver export-policy rule show" -vserver Snapcreator
vserver export-policy show	role create -role vserrbacrole_new -cmddirname "vserver export-policy show" -vserver Snapcreator
Vserver FCP	role create -role vserrbacrole_new -cmddirname "vserver fcp" -vserver Snapcreator
vserver fcp initiator show	role create -role vserrbacrole_new -cmddirname "vserver fcp initiator show" -vserver snapcreator
vserver fcp show	role create -role vserrbacrole_new -cmddirname "vserver fcp show" -vserver snapcreator
SVM FCP 状□	role create -role vserrbacrole_new -cmddirname "vserver fcp status" -vserver snapcreator
SVM iSCSI	role create -role vserrbacrole_new -cmddirname "vserver iscsi" -vserver Snapcreator
vserver iscsi connection show	role create -role vserrbacrole_new -cmddirname "vserver iscsi connection show" -vserver Snapcreator
添加 SVM iSCSI 接口□□列表	role create -role vserrbacrole_new -cmddirname "vserver iscsi interface accesslist add" -vserver Snapcreator
vserver iscsi interface accesslist show	role create -role vserrbacrole_new -cmddirname "vserver iscsi interface accesslist show" -vserver Snapcreator

命令目□名称	要□行的命令
Vserver iSCSI iSNS □□	role create -role vserrbacrole_new -cmddirname "vserver iscsi isns query" -vserver Snapcreator
SVM iSCSI □点名称	role create -role vserrbacrole_new -cmddirname "vserver iscsi nodename -vserver Snapcreator
vserver iscsi session show	role create -role vserrbacrole_new -cmddirname "vserver iscsi session show" -vserver Snapcreator
vserver iscsi show	role create -role vserrbacrole_new -cmddirname "vserver iscsi show" -vserver Snapcreator
SVM iSCSI 状□	role create -role vserrbacrole_new -cmddirname "vserver iscsi status" -vserver Snapcreator
Vserver NFS	role create -role vserrbacrole_new -cmddirname "vserver nfs" -vserver Snapcreator
Vserver NFS 状□	role create -role vserrbacrole_new -cmddirname "vserver nfs status" -vserver Snapcreator
vserver services dns hosts show	role create -role vserrbacrole_new -cmddirname "vserver services name-service dns hosts show" -vserver SnapCreator
vserver services unix-group create	role create -role vserrbacrole_new -cmddirname "vserver services name-service unix-group create" -vserver Snapcreator
vserver services unix-group show	role create -role vserrbacrole_new -cmddirname "vserver services name-service unix-group show" -vserver Snapcreator
vserver services unix-user create	role create -role vserrbacrole_new -cmddirname "vserver services name-service unix-user create" -vserver Snapcreator
vserver services unix-user show	role create -role vserrbacrole_new -cmddirname "vserver services name-service unix-user show" -vserver Snapcreator

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.