什么是 AutoSupport

Snapdrive for Unix

NetApp
July 19, 2022

This PDF was generated from https://docs.netapp.com/zh-cn/snapdrive-unix/aix/concept_how_snapdrive_forunix_usesautosupport.html on July 19, 2022. Always check docs.netapp.com for the latest.

目录

什么是 AutoSupport 1
SnapDrive for UNIX 如何使用 AutoSupport 1
AutoSupport 消息的内容 1
AutoSupport 消息示例 2

什么是 AutoSupport

AutoSupport 允许 SnapDrive for UNIX 将因 SnapDrive 发送到存储系统的 EMS 日志视图中的 ` /etc/log/EMS` 文件而发生的任何操作故障发送到 EMS 日志视图。

SnapDrive for UNIX 如何使用 AutoSupport

如果在 `snapdrive.conf` 文件中将 ` napdrive.conf` 选项设置为 on ，则 AutoSupport 消息将记录在存储系统的 EMS 日志视图中。默认情况下，在 `snapdrive.conf` 文件中，此选项设置为 ` *on*` 。SnapDrive for UNIX 会将 AutoSupport 消息发送到存储系统，而这些消息会记录在事件管理系统（ EMS ）中。

在以下任一情况下都会发送 AutoSupport 消息：

- 如果操作因操作失败而停止，则会向操作失败的存储系统发送 AutoSupport 消息。
- 如果将多个存储系统连接到主机，并且多个存储系统发生操作故障，则 SnapDrive for UNIX 会将 AutoSupport 消息发送到操作失败的特定存储系统。
- 使用 ` UNIX 配置集 < 用户名 > < 文件名 >_` 添加新存储控制器时， SnapDrive for AutoSupport 会向指定的存储系统发送 SnapDrive 消息。
- 重新启动或启动 SnapDrive 守护进程后， AutoSupport 消息将发送到配置的存储系统。
- 执行 SnapDrive storage show -all` 命令后， AutoSupport 消息将发送到所有已配置的存储系统。
- 成功执行快照创建操作后， AutoSupport 消息将发送到存储系统。

AutoSupport 消息的内容

AutoSupport 消息包含以下信息。

- 事件源
- 事件 ID
- 适用于 UNIX 的 SnapDrive 版本
- 消息状态：日志级别消息，例如 1 表示警报， 2 表示严重， 3 表示错误， 4 表示警告， 5 表示通知， 6 表示信息， 7 表示调试
- 主机名
- 主机操作系统
- 主机操作系统的版本
- 存储系统的名称
- 使用 Protection Manager/ 基于角色的访问控制
- 错误类别
- AutoSupport 将消息条目标记为 false
- 主机多路径类型：将记录在 `snapdrive.conf` file 中配置的值。如果由于配置值不正确而未加载此助手，

则不会记录任何主机多路径类型。

- 主机虚拟化已启用：此功能仅适用于 VMware 子操作系统。
- protocol ： 在 `snapdrive.conf` 文件中为 ` 默认传输 _` 配置的值。
- 保护已启用：如果 OnCommand Data Fabric Manager （ DFM ）配置了 SnapDrive for UNIX ，则会记录值 ` *Yes*` 。

> SnapDrive for UNIX 不会验证是否正在使用 OnCommand DFM 。

运行 SnapDrive storage show -all` 命令时，可以使用以下追加信息：

- 协议类型（ FCP/iSCSI ）：用于创建 LUN 的协议（如果有）。
- 已连接的 LUN 数量
- 磁盘或卷组的数量
- 文件规范的数量
- 主机卷的数量

> 如果在 SnapDrive for UNIX 中启用了 AutoSupport ，则在发生任何操作失败时，事件管理系统（ Event Management System ， VM ）存储系统中会记录错误消息。如果错误消息包含任何特殊字符，例如（ < ， > ， & ， ' ， " ， \r ），在存储系统的 EMS 日志视图中会显示格式错误的值。

AutoSupport 消息示例

SnapDrive for UNIX 提供了适用于不同情形的示例。无论您的操作系统如何，所有示例中的 AutoSupport 消息内容都基本相同。

示例：添加新存储系统

以下示例是从名为 ` *aix207-116*` 的主机发送的消息：

```
computerName="aix207-116"
        eventSource="snapdrive"
        appVersion="5.2 for UNIX"
        eventID="3"
        category="ohio configured"
        subject="host_name=aix207-116, host_os=AIX, host_os_release=1,
host_os_version=6, No of controller=1, PM/RBAC=native, Host
Virtualization=No, Multipath-type=nativempio, Protection Enabled=No,
Protocol=fcp"
```

示例：重新启动守护进程

重新启动守护进程时， SnapDrive for UNIX 会向存储系统发送以下 AutoSupport 消息：

```
computerName="aix207-116"
        eventSource="snapdrive"
        appVersion="5.2 for UNIX"
        eventID="2"
        category="daemon restarted"
        subject="host_name=aix207-116, host_os=AIX, host_os_release=1,
host_os_version=6, No of controller=1, PM/RBAC=native, Host
Virtualization=No, Multipath-type=nativempio, Protection Enabled=No,
Protocol=fcp"
```

当存储连接操作失败时， SnapDrive for UNIX 会向存储系统发送以下 AutoSupport 消息：

```
computerName="aix207-116"
        eventSource="snapdrive"
        appVersion="5.2 for UNIX"
        eventID="4"
        category="storage connect failed"
        subject="host_name=aix207-116, host_os=AIX, host_os_release=1,
host_os_version=6, No of controller=1, PM/RBAC=native, Host
Virtualization=No, Multipath-type=nativempio, Protection Enabled=No,
Protocol=fcp,1384: LUN /vol/vol0/test1 on storage system ohio already
mapped to initiators in igroup aix207-116_fcp_SdIg at ID 0."/
```

当 `snap create` 操作成功时， SnapDrive for UNIX 会向存储系统发送以下 AutoSupport 消息：

```
computerName="aix207-116"
        eventSource="snapdrive"
        appVersion="5.2 for UNIX"
        eventID="5"
        category="snap create successful"
        subject="host_name=aix207-116, host_os=AIX, host_os_release=1,
host_os_version=6, No of controller=1, PM/RBAC=native, Host
Virtualization=No, Multipath-type=nativempio, Protection Enabled=No,
Protocol=fcp, snapshot_name=snap1"
```

版权信息

版权所有©2022 NetApp、Inc.。保留所有权利。Printed in the U.S.版权所涵盖的本文档的任何部分不得以任何形式或任何手段复制、包括影印、录制、 磁带或存储在电子检索系统中—未经版权所有者事先书面许可。

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

本软件由NetApp按"原样"提供、不含任何明示或默示担保、包括但不限于适销性和特定用途适用性的默示担保、特此声明不承担任何责任。IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice.NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp.The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S.patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

商标信息

NetApp、NetApp标识和中列出的标记 http://www.netapp.com/TM 是NetApp、Inc.的商标。其他公司和产品名称可能是其各自所有者的商标。