什麼是呢AutoSupport

Snapdrive for Unix

NetApp
May 03, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/snapdrive-unix/aix/concept_how_snapdrive_forunix_usesautosupport.html on May 03, 2022. Always check docs.netapp.com for the latest.

目錄

什麼是呢AutoSupport 1
UNIX版的功能SnapDrive AutoSupport 1
內容AutoSupport 1
範例AutoSupport 2

什麼是呢AutoSupport

支援UNIX的支援功能、可將因執行故障而產生的任何故障、傳送至儲存系統的EMS記錄檢視（位於「/etc/log/EMS」檔案中）AutoSupport SnapDrive SnapDrive 。

UNIX版的功能SnapDrive AutoSupport

當在「snapdrive.conf」檔案中將「*autosup-enabled*」選項設定為「On」時、系統會在儲存系統的EMS記錄檢視中記錄資訊。AutoSupport根據預設、此選項會在「snapdrive.conf」檔案中設為「*on*」。適用於UNIX的解決方案會將不真實的訊息傳送至儲存系統、並將訊息記錄在事件管理系統（EMS）中。SnapDrive AutoSupport

下列任一案例中都會傳送一則消息：AutoSupport

- 當作業因作業失敗而停止時、AutoSupport 會傳送一個消息到作業失敗的儲存系統。
- 如果有多個儲存系統連線至主機、且多個儲存系統發生作業故障、SnapDrive 則適用於UNIX的整套功能AutoSupport 會將此資訊傳送至作業失敗的特定儲存系統。
- 當使用「SnapDrive *esfconfig set <username><filename>*」新增儲存控制器時、SnapDrive 適用於UNIX的Sf2會將AutoSupport 一個「不實」訊息傳送至指定的儲存系統。
- 當重新啟動或啟動此程式時、會將此資訊傳送至設定的儲存系統。SnapDrive AutoSupport
- 當執行「SnapDrive Sof storage show -all」命令時、AutoSupport 會將該訊息傳送至所有已設定的儲存系統。
- 當快照建立作業成功時、AutoSupport 會將此資訊傳送至儲存系統。

內容AutoSupport

包含下列資訊的資訊。AutoSupport

- 事件來源
- 事件ID
- 適用於UNIX的版本SnapDrive
- 訊息狀態：記錄層級訊息、例如警示1、嚴重2、錯誤3、警告4、通知5、 6、資訊、7、偵錯
- 主機名稱
- 主機作業系統
- 主機作業系統的發行版本
- 儲存系統名稱
- 使用Protection Manager /角色型存取控制
- 錯誤類別
- 將訊息項目標示為假AutoSupport
- 主機多重路徑類型：記錄在「snapdrive.conf」檔案中設定的值。如果由於組態值不正確而未載入助理、則

不會記錄任何主機多重路徑類型。

- 已啟用主機虛擬化：此功能僅適用於VMware來賓作業系統。
- 傳輸協定：在「snapdrive.conf」檔案中設定的「_default-transport」值。
- 啟用保護：如果OnCommand 將SesfData Fabric Manager（DFM）設定SnapDrive 為適用於UNIX的支援、則會記錄值「*Yes*」。

> UNIX版無法驗證是否正在使用此功能。SnapDrive OnCommand

當您執行「SnapDrive flexstorage show -all」命令時、可以取得下列額外資訊：

- 傳輸協定類型（FCP / iSCSI）：用於建立LUN的傳輸協定（如果有）。
- 已連線LUN的數量
- 磁碟或磁碟區群組數
- 檔案規格數量
- 主機磁碟區數量

> 當在UNIX的支援中啟用了支援功能時、任何操作失敗時、錯誤訊息都會記錄在事件管理系統（VM）儲存系統中。AutoSupport SnapDrive如果錯誤訊息包含任何特殊字元、例如（<、>、&、'、"、 \r）、儲存系統的EMS記錄檢視中會顯示亂碼值。

範例AutoSupport

UNIX版提供不同情境的範例。SnapDrive在所有範例中、任何作業系統的資訊內容基本上都相同。AutoSupport

範例：新增儲存系統

下列範例是從名為「_aix207-1116」的主機傳送的訊息：

```
computerName="aix207-116"
        eventSource="snapdrive"
        appVersion="5.2 for UNIX"
        eventID="3"
        category="ohio configured"
        subject="host_name=aix207-116, host_os=AIX, host_os_release=1,
host_os_version=6, No of controller=1, PM/RBAC=native, Host
Virtualization=No, Multipath-type=nativempio, Protection Enabled=No,
Protocol=fcp"
```

範例：重新啟動Daemon

當您重新啟動精靈時、適用於UNIX的功能可將下列資訊傳送至儲存系統：SnapDrive AutoSupport

```
computerName="aix207-116"
        eventSource="snapdrive"
        appVersion="5.2 for UNIX"
        eventID="2"
        category="daemon restarted"
        subject="host_name=aix207-116, host_os=AIX, host_os_release=1,
host_os_version=6, No of controller=1, PM/RBAC=native, Host
Virtualization=No, Multipath-type=nativempio, Protection Enabled=No,
Protocol=fcp"
```

當儲存連線作業失敗時、適用於UNIX的範圍會傳送下列資訊給儲存系統：SnapDrive AutoSupport

```
computerName="aix207-116"
        eventSource="snapdrive"
        appVersion="5.2 for UNIX"
        eventID="4"
        category="storage connect failed"
        subject="host_name=aix207-116, host_os=AIX, host_os_release=1,
host_os_version=6, No of controller=1, PM/RBAC=native, Host
Virtualization=No, Multipath-type=nativempio, Protection Enabled=No,
Protocol=fcp,1384: LUN /vol/vol0/test1 on storage system ohio already
mapped to initiators in igroup aix207-116_fcp_SdIg at ID 0."/
```

當「建立抓取」作業成功時、適用於UNIX的範圍會傳送下列資訊給儲存系統：SnapDrive AutoSupport

```
computerName="aix207-116"
        eventSource="snapdrive"
        appVersion="5.2 for UNIX"
        eventID="5"
        category="snap create successful"
        subject="host_name=aix207-116, host_os=AIX, host_os_release=1,
host_os_version=6, No of controller=1, PM/RBAC=native, Host
Virtualization=No, Multipath-type=nativempio, Protection Enabled=No,
Protocol=fcp, snapshot_name=snap1"
```

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.