如何登录和注销
StorageGRID

NetApp
May 17, 2022

This PDF was generated from https://docs.netapp.com/zh-cn/storagegrid-116/tenant/signing-in-to-tenant-manager.html on May 17, 2022. Always check docs.netapp.com for the latest.

目录

如何登录和注销 1
登录到租户管理器 1
注销租户管理器 3

如何登录和注销

登录到租户管理器

您可以通过在的地址栏中输入租户的 URL 来访问租户管理器 支持的 Web 浏览器。

您需要什么？ **#8217**；将需要什么

- 您必须拥有登录凭据。
- 您必须具有网格管理员提供的用于访问租户管理器的 URL 。URL 将类似于以下示例之一：

```
https://FQDN_or_Admin_Node_IP/
```

```
https://FQDN_or_Admin_Node_IP:port/
```

```
https://FQDN_or_Admin_Node_IP/?accountId=20-digit-account-id
```

```
https://FQDN_or_Admin_Node_IP:port/?accountId=20-digit-account-id
```

  此 URL 始终包含用于访问管理节点的完全限定域名（ FQDN ）或 IP 地址，也可以包括端口号， 20 位租户帐户 ID 或这两者。

- 如果 URL 不包含租户的 20 位帐户 ID ，则必须具有此帐户 ID 。
- 您必须使用 支持的 Web 浏览器。
- 必须在 Web 浏览器中启用 Cookie 。
- 您必须具有特定的访问权限。

步骤

1. 启动 支持的 Web 浏览器。
2. 在浏览器的地址栏中，输入用于访问租户管理器的 URL 。
3. 如果系统提示您显示安全警报，请使用浏览器的安装向导安装证书。
4. 登录到租户管理器。

   您看到的登录屏幕取决于您输入的 URL 以及您的组织是否使用单点登录（ SSO ）。您将看到以下屏幕之一：

   - 网格管理器登录页面。单击右上角的 * 租户登录 * 链接。



- 租户管理器登录页面。* 帐户 ID* 字段可能已完成，如下所示。



  i. 如果未显示租户的 20 位帐户 ID ，请选择最近帐户列表中显示的租户帐户名称，或者输入帐户 ID 。
  ii. 输入用户名和密码。
  iii. 单击 * 登录 * 。

  此时将显示租户管理器信息板。

- 如果在网格上启用了 SSO ，则为您所在组织的 SSO 页面。例如：



输入标准 SSO 凭据，然后单击 * 登录 * 。

- 租户管理器 SSO 登录页面。

i. 如果未显示租户的 20 位帐户 ID ，请选择最近帐户列表中显示的租户帐户名称，或者输入帐户 ID 。
ii. 单击 * 登录 * 。
iii. 在您组织的 SSO 登录页面上使用您的标准 SSO 凭据登录。

   此时将显示租户管理器信息板。

5. 如果您从其他人收到初始密码，请更改密码以保护您的帐户。选择 * 。 username_* > * 更改密码 * 。

> 如果为 StorageGRID 系统启用了 SSO ，则无法从租户管理器更改密码。

注销租户管理器

使用租户管理器后，您必须注销以确保未经授权的用户无法访问 StorageGRID 系统。根据浏览器 Cookie 设置，关闭浏览器可能无法将您从系统中注销。

步骤

1. 找到用户界面右上角的用户名下拉列表。



2. 选择用户名，然后选择 * 注销 * 。
   - 如果未使用 SSO ：

     您已从管理节点注销。此时将显示租户管理器登录页面。

> 如果您已登录到多个管理节点，则必须从每个节点注销。

- 如果启用了 SSO：

  您已从正在访问的所有管理节点中注销。此时将显示 StorageGRID 登录页面。您刚刚访问的租户帐户的名称将在 * 近期帐户 * 下拉列表中列为默认名称，并显示租户的 * 帐户 ID* 。

> 如果启用了 SSO ，并且您还登录到网格管理器，则还必须注销网格管理器才能注销 SSO 。

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.