

Autopilot Training

Desktop team

Global Delivery Support Team




Agenda

1. How to use Windows Autopilot
2. How to install Windows OS
3. How to pre-provision laptop
4. Troubleshooting


What is Windows Autopilot?

Windows Autopilot is a collection of technologies used to set up and pre-configure new devices, getting them ready for productive use. Windows Autopilot can be used to deploy Windows PCs.




Read more: <https://learn.microsoft.com/en-us/autopilot/windows-autopilot>

What is Windows Autopilot?




How to using it?

- 1. Access to Microsoft Intune <https://intune.microsoft.com/>



How to using it?

2. Select to Devices -> Windows



How to using it?

3. Select to Windows enrollment -> Devices

Home > Devices | Windows > Windows

Windows | Windows enrollment

Search

Windows devices

Windows enrollment

Windows policies

Compliance policies

Configuration profiles

Scripts and remediations

Update rings for Windows 10 and later

Feature updates for Windows 10 and later

Quality updates for Windows 10 and later

Driver updates for Windows 10 and later

Windows Hello for Business

Replace passwords with strong two-factor authentication.

Windows Autopilot

Use Windows Autopilot to customize the Windows onboarding out of box experience and workflow. [Learn more about Windows Autopilot](#)

Devices

Manage Windows Autopilot devices.

Deployment profiles

Customize the Windows Autopilot provisioning experience.

Enrollment Status Page

Show app and profile installation statuses to users during device setup.

Intune Connector for Active Directory

Configure hybrid Azure AD joined devices.

agoda

Internal | Confidential © 2024 Agoda. All rights reserved.

How to using it?

Overview of Autopilot Devices

[Home](#) > [Devices | Windows](#) > [Windows | Windows enrollment](#) >

Windows Autopilot devices

Windows enrollment

Refresh Export Columns Sync Import Assign user Delete Unblock device

Add filters

Windows Autopilot lets you customize the out-of-box experience (OOBE) for your users.

Last successful sync

05/29/2024, 07:59 PM

Last sync request

05/29/2024, 07:59 PM

☐	Serial number	Manufacturer	Model	Group tag	Profile status
☐	000178591953	Microsoft Corporation	Surface Pro 6		Not assigned
☐	001780592757	Microsoft Corporation	Surface Laptop 2		Not assigned
☐	003205474653	Microsoft Corporation	Surface Pro	Autopilot-Azure-IT	Assigned
☐	004455311957	Microsoft Corporation	Surface Book 3	Autopilot-Azure	Assigned
☐	008503593453	Microsoft Corporation	Surface Pro 6		Not assigned
☐	009378192953	Microsoft Corporation	Surface Pro 6		Not assigned
☐	009466392953	Microsoft Corporation	Surface Pro 6		Not assigned

Type of Group tag

1. Autopilot-Azure-IT

- Group tag for IT user.

2. Autopilot-Azure-CEG

- Group tag for CEG agent user.

3. Autopilot-Azure-CN

- Group tag for user in China.

4. Autopilot-Azure

- Group tag for non-IT and non CEG user.

5. Autopilot-NUC

- Group tag for Dataview machine.

How to set group tag to machine

Home >

Windows Autopilot devices

Windows enrollment

Refresh

Export

Columns

Sync

Import

Assign user

Delete

Unblock device

Search

Add filters

Windows Autopilot lets you customize the out-of-box experience (OOBE) for your users.

Last successful sync

05/29/2024, 07:59 PM

Last sync request

05/29/2024, 07:59 PM

☐	Serial number	Manufacturer	Model	Group tag	Profile status
☒	000178591953	Microsoft Corporation	Surface Pro 6		Not assigned
☐	001780592757	Microsoft Corporation	Surface Laptop 2		Not assigned
☐	003205474653	Microsoft Corporation	Surface Pro	Autopilot-Azure-IT	Assigned
☐	004455311957	Microsoft Corporation	Surface Book 3	Autopilot-Azure	Assigned
☐	008503593453	Microsoft Corporation	Surface Pro 6		Not assigned
☐	009378192953	Microsoft Corporation	Surface Pro 6		Not assigned
☐	009466392953	Microsoft Corporation	Surface Pro 6		Not assigned

000178591953 - Pr...

Windows Autopilot devices

User

unassigned

Serial number

000178591953

Manufacturer

Microsoft Corporation

Model

Surface Pro 6

Device name

Group tag

Autopilot-Azure

Profile status

Not assigned

Assigned profile

Not assigned

Date assigned

Not assigned


Save

How to set group tag to machine

003205474653	Microsoft Corporation	Surface Pro	Autopilot-Azure-IT	Assigned
004455311957	Microsoft Corporation	Surface Book 3	Autopilot-Azure	Assigned

How to add machine to Windows Autopilot Tenant

Open Windows PowerShell ISE by Run as administrator.



How to add machine to Windows Autopilot Tenant


Click New Script



How to add machine to Windows Autopilot Tenant

Type Script follow below.

```
Set-ExecutionPolicy bypass  
Install-Script -name Get-WindowsAutopilotInfo -force  
Get-WindowsAutopilotInfo -Output C:\temp\Autopilot.csv
```




The screenshot shows the Windows PowerShell ISE interface. The title bar reads 'Administrator: Windows PowerShell ISE'. The menu bar includes 'File', 'Edit', 'View', 'Tools', 'Debug', 'Add-ons', and 'Help'. The toolbar contains various icons for file operations, editing, and execution. The script editor shows a file named 'Untitled1.ps1*' with the following code:

```
1 Set-ExecutionPolicy bypass  
2 Install-Script -name Get-WindowsAutopilotInfo -force  
3 Get-WindowsAutopilotInfo -Output C:\temp\Autopilot.csv  
4
```

How to add machine to Windows Autopilot Tenant

Highlight two row for run it first.




The screenshot shows the Windows PowerShell ISE interface. The title bar reads "Administrator: Windows PowerShell ISE". The menu bar includes "File", "Edit", "View", "Tools", "Debug", "Add-ons", and "Help". The toolbar contains various icons for file operations, editing, and execution. A single tab titled "Untitled1.ps1*" is open. The script content is as follows:

```
1 Set-ExecutionPolicy bypass
2 Install-Script -name Get-WindowsAutopilotInfo -force
3 Get-WindowsAutopilotInfo -Output C:\temp\Autopilot.csv
4
```

The first two lines of the script are highlighted in blue.


How to add machine to Windows Autopilot Tenant

If have any pop-ups, click Yes of All



How to add machine to Windows Autopilot Tenant

Waiting it run.


A terminal window with a dark blue background and a light gray title bar. The title bar contains a back arrow icon. The terminal displays two PowerShell commands. The first command is 'Set-ExecutionPolicy bypass' and the second is 'Install-Script -name Get-WindowsAutopilotInfo -force'. Both commands are preceded by the prompt 'PS C:\Windows\system32>'.

```
PS C:\Windows\system32> Set-ExecutionPolicy bypass
Install-Script -name Get-WindowsAutopilotInfo -force

PS C:\Windows\system32>
```

How to add machine to Windows Autopilot Tenant

Highlight third row to add this machine to tenant



The screenshot shows the Windows PowerShell ISE interface. The title bar reads "Administrator: Windows PowerShell ISE". The menu bar includes "File", "Edit", "View", "Tools", "Debug", "Add-ons", and "Help". The toolbar contains various icons for file operations, editing, and execution. The script editor shows a file named "Untitled1.ps1*" with the following commands:

```
1 Set-ExecutionPolicy bypass
2 Install-Script -name Get-WindowsAutopilotInfo -force
3 Get-WindowsAutopilotInfo -Output C:\temp\Autopilot.csv
4
```

The third line of the script is highlighted in blue.


How to add machine to Windows Autopilot Tenant

Script will export the hardware information to the csv file and save on c:\temp\ folder. Then move it to USB storage for prepare to upload to Autopilot page

```
PS C:\Windows\system32> Set-ExecutionPolicy bypass
Install-Script -name Get-WindowsAutopilotInfo -force

PS C:\Windows\system32> Get-WindowsAutopilotInfo -Output C:\temp\Autopilot.csv
Gathered details for device with serial number: 9Z3NRK2

PS C:\Windows\system32> |
```



How to add machine to Windows Autopilot Tenant

Back to Intune page – Autopilot section. Click Import to upload the csv file to import the hardware information to Intune server. Then waiting for 10-15 minutes.

Microsoft Intune admin center

Home

Dashboard

All services

Explorer

Devices

Apps

Endpoint security

Reports

Users

Groups

Tenant administration

Troubleshooting + support

Home

Windows Autopilot devices

Windows enrollment

RefreshExportColumnsSyncImport

SearchAdd filters

Windows Autopilot lets you customize the out-of-box experience (OOBE) for your

Last successful sync10/10/2025, 10:29 AM

Last sync request10/10/2025, 10:29 AM

☐	Serial number	Manufacturer	Model
☐	010917301053	Microsoft Corp...	Surface Pro 7
☐	015356122257	Microsoft Corp...	Surface Laptop 4
☐	017167614553	Microsoft Corp...	Surface Pro 7+
☐	0F005MX23053BF	Microsoft Corp...	Surface Pro 9
☐	0F005N623053BF	Microsoft Corp...	Surface Pro 9
☐	0F005NR23053BF	Microsoft Corp...	Surface Pro 9
☐	0F00NAR23383BF	Microsoft Corp...	Surface Pro 9
☐	0F00NAX23383BF	Microsoft Corp...	Surface Pro 9
☐	0F00NB623383BF	Microsoft Corp...	Surface Pro 9
☐	0F00PFB23303BF	Microsoft Corp...	Surface Pro 9
☐	0F00PJ823303BF	Microsoft Corp...	Surface Pro 9
☐	0F00PJA23303BF	Microsoft Corp...	Surface Pro 9

Add Autopilot devices

Windows Autopilot devices

Import Windows Autopilot devices from a .CSV file. When assigning users in the .CSV, make sure that you are assigning correct UPNs. [Learn more about formatting requirements here.](#)

Specify the path to the list you want to import.
"Autopilot_G7BLN2.csv"

Formatting results
Total rows: 1
Rows formatted correctly: 1

Click import below to import your devices.

Import

Windows OS

How to install Windows OS

How to install Windows OS?

1. Install via USB Drive
2. Install via Windows MDT

Prepare Windows USB Drive

Insert blank USB which more than 16GB to your laptop and download Windows image from official website. And create bootable USB by Rufus or Etcher software.

Reference:

<https://support.microsoft.com/en-us/windows/create-installation-media-for-windows-99a58364-8c02-206f-aa6f-40c3b507420d>


Install Windows from USB Drive

Need to format the machine before clean install
Windows OS

See more: https://www.youtube.com/watch?v=MZbKNiKb_Qc


Install Windows from USB Drive

1. Plug Windows USB and turn on the laptop and press F12 rapidly to load boot selection screen.




Install Windows from USB Drive

2. Select to boot via Generic Flash Disk



Install Windows from USB Drive

3. Select Time and currency format to English (United States)




Install Windows from USB Drive

4. Click Install Now




Install Windows from USB Drive

5. Check box to accept and click Next




Install Windows from USB Drive

6. Click Custom: Install Windows Only




Install Windows from USB Drive

7. Delete all disk for prepare to install from scratch.




Install Windows from USB Drive

8. When deleted click to Unallocated Space and click Next




Install Windows from USB Drive

9. Waiting it install Windows OS on machine.



Install Windows from USB Drive

10. When it done, will show region selection screen.



Install Windows from MDT


What is MDT?

MDT is a unified collection of tools, processes, and guidance for automating desktop and server deployment. You can use it to create reference images or as a complete deployment solution.

See more: <https://learn.microsoft.com/en-us/previous-versions/windows/it-pro/windows-10/deployment/deploy-windows-mdt/get-started-with-the-microsoft-deployment-toolkit>

How to Install Windows from MDT

1. Plug laptop to VLAN 15 network via LAN. Turn on laptop and press F12 to boot to selection boot screen.



How to Install Windows from MDT


2. Select to boot via IPv4

- Onboard IPv4 if connect with LAN port
- USB IPv4 if connect via LAN adaptor

```
Use the ↑(Up) and ↓(Down) arrow keys to move the pointer to the desired boot device.  
Press [Enter] to attempt the boot or ESC to Cancel. (* = Password Required)  
Warning: Legacy boot mode does not support OS boot on internal storage devices  
such as HDD, SSD, NVMe, or eMMC. It is intended for use with external storage devices only,  
such as SD Card, USB, and Network PXE.  
  
Boot mode is set to: UEFI; Secure Boot: ON  
  
UEFI BOOT:  
  UEFI: SK hynix SC401 SATA 256GB  
  Onboard NIC(IPV4)  
  Onboard NIC(IPV6)  
OTHER OPTIONS:  
  BIOS Setup  
  BIOS Flash Update  
  Diagnostics  
  Change Boot Mode Settings  
  
OptiPlex 3060          BIOS Revision 1.25.0          Dell
```


How to Install Windows from MDT

3. Select to boot Autopilot




How to Install Windows from MDT

4. Select the sequence option which you want to install and click Next.



How to Install Windows from MDT

5. Waiting to the MDT install until show Region selection screen.




Prepare laptop to pre-provision

Updates Windows patch


1. After install Windows OS. Before pre-provision. Need to updates Windows Patch.

In region selection screen. Press Ctrl+Shift+F3 to skip OOB to access to Desktop.




Updates Windows patch

2 . Click Start and type “update” and click Check Updates.




Updates Windows patch

3. Click updates until it no patch to updates. And click Sysprep to back to OOBE.




Pre-Provisioning

4. Press Windows button 5 times to access pre-provisioning page and select Pre-Provisioning.




Pre-Provisioning

5. It's will show the detail of Group tag which assign to this machine. Click Next.




Pre-Provisioning

6. Waiting it enroll machine and install application.



Pre-Provisioning

7. When it's done, it will show summary screen and click Reseal to turn off. Ready to delivery!



Troubleshooting

Why can't add Group tag to machine?

Enable Intune Admin role before add group tag.

[Link](#)

Microsoft Entra admin center

Search resources, services, and docs (G+)

Home

What's new

Diagnose & solve problems

Favorites

Identity

Overview

Users

Groups

Home > My roles

My roles | Groups

Privileged Identity Management | My roles

Activate

Microsoft Entra roles

Groups

Azure resources

Troubleshooting + Support

Troubleshoot

New support request

Refresh

Got feedback?

Eligible assignments

Active assignments


Expired assignments

Search by role or group

Role	Group	Group type	Membership	End time	Action
Member	Intune-Role-GSD-L1-L2	Security	Group	Permanent	Activate

Why can't pre-provisioning?

Didn't assign Group tag for that machine.



Serial number	Manufacturer	Model	Group tag	Profile status
4557500153	Microsoft Corporation	Surface Pro 7		Not assigned