

Hostname:

```
[sudo] password for berserk-jump:
Static hostname: Centos-jump-OYL
Icon name: computer-vm
Chassis: vm 🖥️
Machine ID: f325b32d438240979ed683dbebe88db9
Boot ID: 02b2a5bbf2794fee8d62394fd485877e
Product UUID: 31b5c1c2-5be5-4ff1-9ff5-26a75babd9e7
Virtualization: kvm
Operating System: CentOS Stream 10 (Coughlan)
CPE OS Name: cpe:/o:centos:centos:10
Kernel: Linux 6.12.0-257.el10.x86_64
Architecture: x86-64
Hardware Vendor: QEMU
Hardware Model: Standard PC _Q35 + ICH9, 2009_
Firmware Version: 1.17.0-10.fc44
Firmware Date: Tue 2025-06-10
Firmware Age: 1y 2month 1d
[berserk-jump@Centos-jump-OYL ~]$
```

Updated system:

```
[berserk-jump@Centos-jump-OYL ~]$ sudo dnf upgrade
Last metadata expiration check: 0:24:07 ago on 2026-08-11T14:47:21 CEST.
Dependencies resolved.
Nothing to do.
Complete!
[berserk-jump@Centos-jump-OYL ~]$
```

Packages installed:

```
[berserk-jump@Centos-jump-OYL ~]$ rpm -q nano vim-enhanced dnf-automatic
nano-8.1-3.el10.x86_64
vim-enhanced-9.1.083-22.el10.x86_64
dnf-automatic-4.20.0-27.el10.noarch
[berserk-jump@Centos-jump-OYL ~]$
```

Users exist:

```
[berserk-jump@Centos-jump-OYL ~]$ id pingu
id berserk-jump
uid=1000(pingu) gid=1000(pingu) groups=1000(pingu),10(wheel),1002(allow_ssh)
uid=1001(berserk-jump) gid=1001(berserk-jump) groups=1001(berserk-jump),10(wheel),1002(allow_ssh)
[berserk-jump@Centos-jump-OYL ~]$
```

Groups & Users:

```
[berserk-jump@Centos-jump-OYL ~]$ id pingu
uid=1000(pingu) gid=1000(pingu) groups=1000(pingu),10(wheel),1002(allow_ssh)
[berserk-jump@Centos-jump-OYL ~]$ id berserk-jump
uid=1001(berserk-jump) gid=1001(berserk-jump) groups=1001(berserk-jump),10(wheel),1002(allow_ssh)
[berserk-jump@Centos-jump-OYL ~]$ getent group allow_ssh
allow_ssh:x:1002:pingu,berserk-jump
[berserk-jump@Centos-jump-OYL ~]$
```

SELinux:

```
[berserk-jump@Centos-jump-OYL ~]$ grep ^SELINUX= /etc/selinux/config
SELINUX=permissive
Permissive
[berserk-jump@Centos-jump-OYL ~]$
```

SSH:

```
[berserk-jump@Centos-jump-OYL ~]$ sudo grep AllowGroups /etc/ssh/sshd_config
[sudo] password for berserk-jump:
AllowGroups allow_ssh
```

dnf-automatic:

```
[berserk-jump@Centos-jump-OYL ~]$ grep -E 'upgrade_type|apply_updates' /etc/dnf/automatic.conf
systemctl is-enabled dnf-automatic.timer
systemctl is-active dnf-automatic.timer
systemctl status dnf-automatic.timer --no-pager
upgrade_type = default
apply_updates = no
disabled
inactive
o dnf-automatic.timer - dnf-automatic timer
   Loaded: loaded (/usr/lib/systemd/system/dnf-automatic.timer; disabled; preset: disabled)
   Active: inactive (dead)
   Trigger: n/a
   Triggers: ● dnf-automatic.service
```

Firewall:

```
[berserk-jump@Centos-jump-OYL ~]$ sudo firewall-cmd --list-all --zone=internal
internal (active)
  target: default
  ingress-priority: 0
  egress-priority: 0
  icmp-block-inversion: no
  interfaces: enp1s0
  sources:
  services: ssh
  ports: 22/tcp
  protocols:
  forward: yes
  masquerade: no
  forward-ports:
  source-ports:
  icmp-blocks:
  rich rules:
[berserk-jump@Centos-jump-OYL ~]$
```