


Internet Protocol (TCP/IP) Properties



General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address:

192 . 50 . 20 . 100

Subnet mask:

255 . 255 . 255 . 0

Default gateway:

192 . 50 . 20 . 1

☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:

Preferred DNS server:

Alternate DNS server:

Advanced...

OK

Cancel

Internet Protocol (TCP/IP) Properties

General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address:

223 . 0 . 50 . 10

Subnet mask:

255 . 255 . 255 . 0

Default gateway:

223 . 0 . 50 . 1

☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:

Preferred DNS server:

. . . .

Alternate DNS server:

. . . .

Advanced...

OK

Cancel

Internet Protocol (TCP/IP) Properties



General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address:

172 . 36 . 0 . 10

Subnet mask:

255 . 255 . 0 . 0

Default gateway:

172 . 36 . 0 . 1

☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:

Preferred DNS server:

Alternate DNS server:

Advanced...

OK

Cancel

R1#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

R1(config)#interface ethernet0/0

R1(config-if)#192.50.20.1 255.255.255.0

^

% Invalid input detected at '^' marker.

R1(config-if)#ip add 192.50.20.1 255.255.255.0

R1(config-if)#no shutdown

R1(config-if)#exit

R1(config)#interface ethernet0/1\

^

% Invalid input detected at '^' marker.

R1(config)#interface ethernet0/1

R1(config-if)#ip add 12.0.0.1 255.0.0.0

I

R1(config-if)#no shutdown

R1(config-if)#exit

R1(config)#exit

R1#

*Aug 26 16:46:10.474: %SYS-5-CONFIG_I: Configured from console by console

R1#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
Ethernet0/0	192.50.20.1	YES	manual	up	up
Ethernet0/1	12.0.0.1	YES	manual	up	up
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

R1#

*Aug 26 16:46:18.431: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)

R1#

```
R2#
R2#
R2#
R2#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#int e0/0
R2(config-if)#ip add 12.0.0.2 255.0.0.0
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#int e0/1
R2(config-if)#ip add 26.0.0.1 255.0.0.0
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#int e0/2
R2(config-if)#ip add 23.0.0.1 255.0.0.0
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#int e0/3
R2(config-if)#ip add 24.0.0.1 255.0.0.0
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#exit
R2#
*Aug 26 16:52:08.600: %SYS-5-CONFIG_I: Configured from console by console
```

```
R2#show ip interface brief
```

Interface	IP-Address	OK?	Method	Status	Protocol
Ethernet0/0	12.0.0.2	YES	manual	up	up
Ethernet0/1	26.0.0.1	YES	manual	up	up
Ethernet0/2	23.0.0.1	YES	manual	up	up
Ethernet0/3	24.0.0.1	YES	manual	up	up

```
R2#
```

```
*Aug 26 16:53:22.716: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
```

```
R2#
```

```
R3#config t
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#
*Aug 26 16:55:17.463: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R3(config)#int e0/0
R3(config-if)#ip add 23.0.0.2 255.0.0.0
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#int e0/1
R3(config-if)#ip add 32.0.0.1 255.0.0.0
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#exit
R3#
*Aug 26 16:58:14.534: %SYS-5-CONFIG_I: Configured from console by console
R3#show ip interface brief
^
% Invalid input detected at '^' marker.

R3#show ip interface brief
Interface                IP-Address      OK? Method Status    Protocol
Ethernet0/0              23.0.0.2        YES manual  up        up
Ethernet0/1              32.0.0.1        YES manual  up        up
Ethernet0/2              unassigned      YES TFTP   down      down
Ethernet0/3              unassigned      YES TFTP   down      down
R3#
```

% Ambiguous command: "ip a"

R4(config-if)#exit

R4(config)#exit

R4#

*Aug 26 17:01:49.731: %SYS-5-CONFIG_I: Configured from console by console

R4#config t

Enter configuration commands, one per line. End with CNTL/Z.

R4(config)#int e0/0

R4(config-if)#ip add 24.0.0.2 255.0.0.0

R4(config-if)#no shutdown

R4(config-if)#exit

R4(config)#int e0/1

R4(config-if)#ip add 45.0.0.1 255.0.0.0

R4(config-if)#no shutdown

R4(config-if)#exit

R4(config)#exit

R4#sho

*Aug 26 17:03:16.030: %SYS-5-CONFIG_I: Configured from console by console

R4#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
Ethernet0/0	24.0.0.2	YES	manual	up	up
Ethernet0/1	45.0.0.1	YES	manual	up	up
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

R4#

R5#config t

Enter configuration commands, one per line. End with CNTL/Z.

R5(config)#int e0/0

R5(config-if)#ip add 172.36.0.1 255.255.0.0

R5(config-if)#no shutdown

R5(config-if)#exit

R5(config)#int e0/1

R5(config-if)#ip add 32.0.0.2 255.0.0.0

R5(config-if)#no shutdown

R5(config-if)#exit

R5(config)#int e0/2

R5(config-if)#ip ad 45.0.0.2 255.0.0.0

% Ambiguous command: "ip ad 45.0.0.2 255.0.0.0"

R5(config-if)#ip ad 45.0.0.2 255.0.0.0

*Aug 26 17:06:13.159: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)

R5(config-if)#ip add 45.0.0.2 255.0.0.0

R5(config-if)#no shutdown

R5(config-if)#exit

R5(config)#exit

R5#sh

*Aug 26 17:06:28.396: %SYS-5-CONFIG_I: Configured from console by console

R5#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
Ethernet0/0	172.36.0.1	YES	manual	up	up
Ethernet0/1	32.0.0.2	YES	manual	up	up
Ethernet0/2	45.0.0.2	YES	manual	up	down
Ethernet0/3	unassigned	YES	TFTP	down	

R5#

```

R6#config t
Enter configuration commands, one per line. End with CNTL/Z.
R6(config)#int e0/0
R6(config-if)#ip add 223.
*Aug 26 17:08:12.774: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R6(config-if)#ip add 223.0.50.1 255.255.255.0
R6(config-if)#no shutdown
R6(config-if)#exit
R6(config)#int e0/1
R6(config-if)#ip add 26.0.0.2 255.0.0.0
R6(config-if)#no shutdown
R6(config-if)#exit
R6(config)#exit
R6#show
*Aug 26 17:09:24.427: %SYS-5-CONFIG_I: Configured from console by console
R6#show ip interface brief

```

Interface	IP-Address	OK?	Method	Status	Protocol
Ethernet0/0	223.0.50.1	YES	manual	up	up
Ethernet0/1	26.0.0.2	YES	manual	up	up
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

```

R6#

```

```
R1(config)#ip route 23.0.0.0 255.0.0.0 12.0.0.2
R1(config)#ip route 32.0.0.0 255.0.0.0 12.0.0.2
R1(config)#ip route 172.36.0.0 255.255.0.0 12.0.0.2
R1(config)#ip route 26.0.0.0 255.0.0.0 12.0.0.2
R1(config)#ip route 233.0.50.0 255.255.255.0 12.0.0.2
% Invalid destination prefix
R1(config)#ip route 223.0.50.0 255.255.255.0 12.0.0.2
R1(config)#24.0.0.0 255.0.0.0 12.0.0.2
```

% Invalid input detected at '^' marker.

```
R1(config)#ip route 24.0.0.0 255.0.0.0 12.0.0.2
R1(config)#ip route 45.0.0.0 255.0.0.0 12.0.0.2
R1(config)#exit
R1#
```

*Aug 27 06:15:53.749: %SYS-5-CONFIG_I: Configured from console by console

```
R1#show ip route
```

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

```
12.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C    12.0.0.0/8 is directly connected, Ethernet0/1
L    12.0.0.1/32 is directly connected, Ethernet0/1
S    23.0.0.0/8 [1/0] via 12.0.0.2
S    24.0.0.0/8 [1/0] via 12.0.0.2
S    26.0.0.0/8 [1/0] via 12.0.0.2
S    32.0.0.0/8 [1/0] via 12.0.0.2
```

```
R2#config t
```

```
Enter configuration commands, one per line. End with CNTL/Z.
```

```
R2(config)#ip route 192.50.20.0 255.255.255.0 12.0.0.1
```

```
R2(config)#ip route 223.0.50.0 255.255.255.0 26.0.0.2
```

```
R2(config)#ip route 32.0.0.0 255.0.0.0 23.0.0.2
```

```
R2(config)#ip route 172.36.0.0 255.255.0.0 23.0.0.2
```

```
R2(config)#ip route 45.0.0.0 255.0.0.0 24.0.0.2
```

```
R2(config)#exit
```

```
R2#s
```

```
*Aug 27 06:21:57.902: %SYS-5-CONFIG_I: Configured from console by console
```

```
R2#show ip route
```

```
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP  
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area  
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2  
E1 - OSPF external type 1, E2 - OSPF external type 2  
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2  
ia - IS-IS inter area, * - candidate default, U - per-user static route  
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP  
a - application route  
+ - replicated route, % - next hop override, p - overrides from PfR
```

```
Gateway of last resort is not set
```

```
12.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
```

```
C    12.0.0.0/8 is directly connected, Ethernet0/0
```

```
L    12.0.0.2/32 is directly connected, Ethernet0/0
```

```
23.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
```

```
C    23.0.0.0/8 is directly connected, Ethernet0/2
```

```
L    23.0.0.1/32 is directly connected, Ethernet0/2
```

```
24.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
```

```
C    24.0.0.0/8 is directly connected, Ethernet0/3
```

```
L    24.0.0.1/32 is directly connected, Ethernet0/3
```

```
26.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
```

```
--More--
```

R1 x R2 x R3 x R4 x R5 x R6 x Win-1 x Win-2 x Win-3 x

R3#config t

Enter configuration commands, one per line. End with CNTL/Z.

R3(config)#ip route 192.50.20.0 255.255.255.0 23.0.0.1

R3(config)#ip route 12.0.0.0 255.0.0.0 23.0.0.1

R3(config)#ip route 172.36.0.0 255.255.0.0 32.0.0.2

R3(config)#ip route 24.0.0.0 255.0.0.0 24.0.0.1

R3(config)#ip route 45.0.0.0 255.0.0.0 45.0.0.2

R3(config)#ip route 26.0.0.0 255.0.0.0 23.0.0.1

R3(config)#ip route 223.0.50.0 255.255.255.0 23.0.0.1

R3(config)#exit

R3#sh

*Aug 27 06:28:05.351: %SYS-5-CONFIG_I: Configured from console by console

R3#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

S 12.0.0.0/8 [1/0] via 23.0.0.1
23.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C 23.0.0.0/8 is directly connected, Ethernet0/0
L 23.0.0.2/32 is directly connected, Ethernet0/0
S 26.0.0.0/8 [1/0] via 23.0.0.1
32.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C 32.0.0.0/8 is directly connected, Ethernet0/1
L 32.0.0.1/32 is directly connected, Ethernet0/1
S 172.36.0.0/16 [1/0] via 32.0.0.2
S 192.50.20.0/24 [1/0] via 23.0.0.1

--More--

```
R4(config)#ip route 192.50.20.0 255.255.255.0 24.0.0.1
R4(config)#ip route 12.0.0.0 255.0.0.0 24.0.0.1
R4(config)#ip route 26.0.0.0 255.0.0.0 24.0.0.1
R4(config)#ip route 223.0.50.0 255.255.255.0 24.0.0.1
R4(config)#ip route 172.36.0.0 255.255.0.0 45.0.0.2
R4(config)#ip route 23.0.0.2 255.0.0.0 23.0.0.1
%Inconsistent address and mask
R4(config)#ip route 23.0.0.0 255.0.0.0 23.0.0.1
R4(config)#ip route 32.0.0.0 255.0.0.0 32.0.0.2
R4(config)#exit
R4#sh
```

*Aug 27 06:34:16.412: %SYS-5-CONFIG_I: Configured from console by console

R4#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
 D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
 N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
 E1 - OSPF external type 1, E2 - OSPF external type 2
 i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
 ia - IS-IS inter area, * - candidate default, U - per-user static route
 o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
 a - application route
 + - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

```
S    12.0.0.0/8 [1/0] via 24.0.0.1
    24.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C    24.0.0.0/8 is directly connected, Ethernet0/0
L    24.0.0.2/32 is directly connected, Ethernet0/0
S    26.0.0.0/8 [1/0] via 24.0.0.1
    45.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C    45.0.0.0/8 is directly connected, Ethernet0/1
L    45.0.0.1/32 is directly connected, Ethernet0/1
S    172.36.0.0/16 [1/0] via 45.0.0.2
S    192.50.20.0/24 [1/0] via 24.0.0.1
```

-More--

Enter configuration commands, one per line. End with CNTL/Z.

R5(config)#ip route 192.50.20.0 255.255.255.0 32.0.0.1

R5(config)#ip route 12.0.0.0 255.0.0.0 32.0.0.1

R5(config)#ip route 23.0.0.0 255.0.0.0 32.0.0.1

R5(config)#ip route 24.0.0.0 255.0.0.0 45.0.0.1

R5(config)#ip route 26.0.0.0 255.0.0.0 45.0.0.1

R5(config)#ip route 223.0.50.0 255.0.0.0 45.0.0.1

Inconsistent address and mask

R5(config)#ip route 223.0.50.0 255.255.255.0 45.0.0.1

R5(config)#exit

R5#show

Aug 27 06:39:42.195: %SYS-5-CONFIG_I: Configured from console by console

R5#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP

a - application route

+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

S 12.0.0.0/8 [1/0] via 32.0.0.1

S 23.0.0.0/8 [1/0] via 32.0.0.1

S 24.0.0.0/8 [1/0] via 45.0.0.1

S 26.0.0.0/8 [1/0] via 45.0.0.1

32.0.0.0/8 is variably subnetted, 2 subnets, 2 masks

C 32.0.0.0/8 is directly connected, Ethernet0/1

L 32.0.0.2/32 is directly connected, Ethernet0/1

45.0.0.0/8 is variably subnetted, 2 subnets, 2 masks

C 45.0.0.0/8 is directly connected, Ethernet0/2

L 45.0.0.2/32 is directly connected, Ethernet0/2

-- More --

R6#config t

Enter configuration commands, one per line. End with CNTL/Z.

R6(config)#ip route 192.50.20.0 255.255.255.0 26.0.0.1

R6(config)#ip route 12.0.0.0 255.0.0.0 26.0.0.1

R6(config)#ip route 23.0.0.0 255.0.0.0 26.0.0.1

R6(config)#ip route 32.0.0.0 255.0.0.0 26.0.0.1

R6(config)#ip route 172.36.0.0 255.255.0.0 26.0.0.1

R6(config)#ip route 24.0.0.0 255.0.0.0 26.0.0.1

R6(config)#ip route 45.0.0.0 255.0.0.0 26.0.0.1

R6(config)#exit

R6#show

*Aug 27 06:43:03.991: %SYS-5-CONFIG_I: Configured from console by console

R6#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP

a - application route

+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

S 12.0.0.0/8 [1/0] via 26.0.0.1

S 23.0.0.0/8 [1/0] via 26.0.0.1

S 24.0.0.0/8 [1/0] via 26.0.0.1

26.0.0.0/8 is variably subnetted, 2 subnets, 2 masks

C 26.0.0.0/8 is directly connected, Ethernet0/1

L 26.0.0.2/32 is directly connected, Ethernet0/1

S 32.0.0.0/8 [1/0] via 26.0.0.1

S 45.0.0.0/8 [1/0] via 26.0.0.1

S 172.36.0.0/16 [1/0] via 26.0.0.1

S 192.50.20.0/24 [1/0] via 26.0.0.1

--More--

C:\WINDOWS\system32\cmd.exe

Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ping 223.0.50.10

Pinging 223.0.50.10 with 32 bytes of data:

Reply from 223.0.50.10: bytes=32 time=4ms TTL=125
Reply from 223.0.50.10: bytes=32 time=2ms TTL=125
Reply from 223.0.50.10: bytes=32 time=2ms TTL=125
Reply from 223.0.50.10: bytes=32 time=1ms TTL=125

Ping statistics for 223.0.50.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 1ms, Maximum = 4ms, Average = 2ms

C:\Documents and Settings\user>

R5 x R6 x Win-1 x Win-2 x Win-3 x

C:\WINDOWS\system32\cmd.exe

Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ping 172.36.0.10

Pinging 172.36.0.10 with 32 bytes of data:

Reply from 172.36.0.10: bytes=32 time=5ms TTL=124
Reply from 172.36.0.10: bytes=32 time=3ms TTL=124
Reply from 172.36.0.10: bytes=32 time=3ms TTL=124
Reply from 172.36.0.10: bytes=32 time=3ms TTL=124

Ping statistics for 172.36.0.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 3ms, Maximum = 5ms, Average = 3ms

C:\Documents and Settings\user>

x R6 x Win-1 x Win-2 x Win-3 x

C:\WINDOWS\system32\cmd.exe

Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ping 192.50.20.100

Pinging 192.50.20.100 with 32 bytes of data:

Reply from 192.50.20.100: bytes=32 time=2ms TTL=125
Reply from 192.50.20.100: bytes=32 time=2ms TTL=125
Reply from 192.50.20.100: bytes=32 time=2ms TTL=125
Reply from 192.50.20.100: bytes=32 time=2ms TTL=125

Ping statistics for 192.50.20.100:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 2ms, Maximum = 2ms, Average = 2ms

C:\Documents and Settings\user>

C:\WINDOWS\system32\cmd.exe

Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ping 172.36.0.10

Pinging 172.36.0.10 with 32 bytes of data:

Reply from 172.36.0.10: bytes=32 time=4ms TTL=124
Reply from 172.36.0.10: bytes=32 time=3ms TTL=124
Reply from 172.36.0.10: bytes=32 time=3ms TTL=124
Reply from 172.36.0.10: bytes=32 time=3ms TTL=124

Ping statistics for 172.36.0.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 3ms, Maximum = 4ms, Average = 3ms

C:\Documents and Settings\user>

C:\WINDOWS\system32\cmd.exe

Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ping 192.50.20.100

Pinging 192.50.20.100 with 32 bytes of data:

Reply from 192.50.20.100: bytes=32 time=3ms TTL=124
Reply from 192.50.20.100: bytes=32 time=3ms TTL=124
Reply from 192.50.20.100: bytes=32 time=2ms TTL=124
Reply from 192.50.20.100: bytes=32 time=2ms TTL=124

Ping statistics for 192.50.20.100:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 2ms, Maximum = 3ms, Average = 2ms

C:\Documents and Settings\user>_

C:\WINDOWS\system32\cmd.exe

Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

G:\Documents and Settings\user>ping 223.0.50.10

Pinging 223.0.50.10 with 32 bytes of data:

Reply from 223.0.50.10: bytes=32 time=4ms TTL=124
Reply from 223.0.50.10: bytes=32 time=1ms TTL=124
Reply from 223.0.50.10: bytes=32 time=2ms TTL=124
Reply from 223.0.50.10: bytes=32 time=2ms TTL=124

Ping statistics for 223.0.50.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 1ms, Maximum = 4ms, Average = 2ms

G:\Documents and Settings\user>