

IP Configuration

Interface FastEthernet0

IP Configuration

☐ DHCP

☒ Static

IPv4 Address

10.0.0.10

Subnet Mask

255.0.0.0

Default Gateway

10.0.0.1

DNS Server

0.0.0.0

IPv6 Configuration

☐ Automatic

☒ Static

IPv6 Address

/

Link Local Address

FE80::2D0:BCFF:FEAE:C82C

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication

MD5

Username

Password

☐ Top

New

Delete

Toggle PDU List Window

Copper Cross-Over



Search



Destination Type C

IP Configuration

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 10.0.0.10

Subnet Mask 255.0.0.0

Default Gateway 10.0.0.1

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::2D0:BCFF:FEAE:C82C

Default Gateway

DNS Server

802.1X


☐ Use 802.1X Security

Authentication MD5

Username

Password

elp



PC3

Physical Config Desktop Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 40.0.0.10

Subnet Mask 255.0.0.0

Default Gateway 40.0.0.1

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address

Link Local Address FE80::20C:CFFF:FE56:3295

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

☐ Top

PC-PT
PC2

Fa0

New


Delete

Toggle PDU List Window

Copper Cross-Over



Search



Destination Typ

IP Configuration

Interface

FastEthernet0

IP Configuration

☐ DHCP

☒ Static

IPv4 Address

40.0.0.10

Subnet Mask

255.0.0.0

Default Gateway

40.0.0.1

DNS Server

0.0.0.0

IPv6 Configuration

☐ Automatic

☒ Static

IPv6 Address

Link Local Address

FE80::20C:CFFF:FE56:3295

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication

MD5

Username

Password

```

Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface f0/0
Router(config-if)#ip add 10.0.0.1 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#interface f0/1
Router(config-if)#ip add 20.0.0.1 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

Router(config-if)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip interface brief

```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	10.0.0.1	YES	manual	up	up
FastEthernet0/1	20.0.0.1	YES	manual	up	down
Vlan1	unassigned	YES	unset	administratively down	down

```

Router#

```

```
Router#show ip interface brief
```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	unassigned	YES	unset	administratively down	down
FastEthernet0/1	unassigned	YES	unset	administratively down	down
Vlan1	unassigned	YES	unset	administratively down	down

```
Router#configure terminal
```

```
Enter configuration commands, one per line. End with CNTL/Z.
```

```
Router(config)#interface f0/0
```

```
Router(config-if)#ip add 20.0.0.2 255.0.0.0
```

```
Router(config-if)#no shutdown
```

```
Router(config-if)#
```

```
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
```

```
Router(config-if)#exit
```

```
Router(config)#interface f0/1
```

```
Router(config-if)#ip add 30.0.0.1 255.0.0.0
```

```
Router(config-if)#no shutdown
```

```
Router(config-if)#
```

```
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
```

```
Router(config-if)#exit
```

```
Router(config)#show ip interface brief
```

```
^
```

```
% Invalid input detected at '^' marker.
```

```
Router(config)#exit
```

```
Router#
```

```
%SYS-5-CONFIG_I: Configured from console by console
```

```
Router#show ip interface brief
```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	20.0.0.2	YES	manual	up	up
FastEthernet0/1	30.0.0.1	YES	manual	up	down
Vlan1	unassigned	YES	unset	administratively down	down

```
Router#
```

Router>enable

Router#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	unassigned	YES	unset	administratively down	down
FastEthernet0/1	unassigned	YES	unset	administratively down	down
Vlan1	unassigned	YES	unset	administratively down	down

Router#config terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface f0/0

Router(config-if)#ip add 30.0.0.2 255.0.0.0

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#exit

Router(config)#interface f0/1

Router(config-if)#ip add 40.0.0.1 255.0.0.0

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

Router(config-if)#exit

Router(config)#exit

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	30.0.0.2	YES	manual	up	up
FastEthernet0/1	40.0.0.1	YES	manual	up	up
Vlan1	unassigned	YES	unset	administratively down	down

Router#

Router#

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#ip route 30.0.0.0 255.0.0.0 20.0.0.2

Router(config)#ip route 40.0.0.0 255.0.0.0 20.0.0.2

Router(config)#exit

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router#show ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP

i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default, U - per-user static route, o - ODR

P - periodic downloaded static route

Gateway of last resort is not set

C 10.0.0.0/8 is directly connected, FastEthernet0/0

C 20.0.0.0/8 is directly connected, FastEthernet0/1

S 30.0.0.0/8 [1/0] via 20.0.0.2

S 40.0.0.0/8 [1/0] via 20.0.0.2

Router#

Router#

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#ip route 10.0.0.0 255.0.0.0 20.0.0.1

Router(config)#ip route 40.0.0.0 255.0.0.0 30.0.0.2

Router(config)#exit

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router#show ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route

Gateway of last resort is not set

S 10.0.0.0/8 [1/0] via 20.0.0.1
C 20.0.0.0/8 is directly connected, FastEthernet0/0
C 30.0.0.0/8 is directly connected, FastEthernet0/1
S 40.0.0.0/8 [1/0] via 30.0.0.2

Router#

Router#

Router#config terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#ip route 10.0.0.0 255.0.0.0 30.0.0.1

Router(config)#ip route 20.0.0.0 255.0.0.0 30.0.0.1

Router(config)#exit

Router#

%SYS-5-CONFIG_I: Configured from console by console

Router#show ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route

Gateway of last resort is not set

S 10.0.0.0/8 [1/0] via 30.0.0.1

S 20.0.0.0/8 [1/0] via 30.0.0.1

C 30.0.0.0/8 is directly connected, FastEthernet0/0

C 40.0.0.0/8 is directly connected, FastEthernet0/1

Router#

C:\>ping 40.0.0.10

Pinging 40.0.0.10 with 32 bytes of data:

Reply from 40.0.0.10: bytes=32 time<1ms TTL=125

Reply from 40.0.0.10: bytes=32 time<1ms TTL=125

Reply from 40.0.0.10: bytes=32 time<1ms TTL=125

Reply from 40.0.0.10: bytes=32 time=1ms TTL=125

Ping statistics for 40.0.0.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\>ping 40.0.0.10

Pinging 40.0.0.10 with 32 bytes of data:

Reply from 40.0.0.10: bytes=32 time<1ms TTL=125

Reply from 40.0.0.10: bytes=32 time<1ms TTL=125

Reply from 40.0.0.10: bytes=32 time<1ms TTL=125

Reply from 40.0.0.10: bytes=32 time=1ms TTL=125

Ping statistics for 40.0.0.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\>

Cisco Packet Tracer PC Command Line 1.0

C:\>ping 10.0.0.10

Pinging 10.0.0.10 with 32 bytes of data:

Reply from 10.0.0.10: bytes=32 time<1ms TTL=125

Reply from 10.0.0.10: bytes=32 time=1ms TTL=125

Reply from 10.0.0.10: bytes=32 time<1ms TTL=125

Reply from 10.0.0.10: bytes=32 time<1ms TTL=125

Ping statistics for 10.0.0.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\>ping 10.0.0.10

Pinging 10.0.0.10 with 32 bytes of data:

Reply from 10.0.0.10: bytes=32 time<1ms TTL=125

Reply from 10.0.0.10: bytes=32 time<1ms TTL=125

Reply from 10.0.0.10: bytes=32 time<1ms TTL=125

Reply from 10.0.0.10: bytes=32 time<1ms TTL=125

Ping statistics for 10.0.0.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>