
How To Use AWS CLI

1 INTRODUCTION

The AWS Command Line Interface (AWS CLI) is an open source tool that enables you to interact with AWS services using commands in your command-line shell. With minimal configuration, the AWS CLI enables you to start running commands that implement functionality equivalent to that provided by the browser-based AWS Management Console from the command prompt in your favorite terminal program:

Linux shells – Use common shell programs such as bash, zsh, and tcsh to run commands in Linux or macOS.

Windows command line – On Windows, run commands at the Windows command prompt or in PowerShell.

Remotely – Run commands on Amazon Elastic Compute Cloud (Amazon EC2) instances through a remote terminal program such as PuTTY or SSH, or with AWS Systems Manager.

The AWS CLI is available in two versions and the information in this guide applies to version 2.x unless stated otherwise:

- **Version 2.x** – The current version, generally available release of the AWS CLI that is intended for use in production environments. This version does include some "breaking" changes from version 1 that might require you to change your scripts so that they continue to operate as you expect.
- **Version 1.x** – The previous version of the AWS CLI that is available for backwards compatibility.

This activity guide cover steps for:

1. Installing AWS CLI on windows.
2. Configuring AWS CLI
3. Setting up AWS SDK

2 DOCUMENTATION LINKS

1. What Is the AWS Command Line Interface?
<https://docs.aws.amazon.com/cli/latest/userguide/cli-chap-welcome.html>
2. How to create AWS Access Keys
<https://aws.amazon.com/premiumsupport/knowledge-center/create-access-key/>
3. Managing Access Keys for IAM Users
https://docs.aws.amazon.com/IAM/latest/UserGuide/id_credentials_access-keys.html#Using_CreateAccessKey


3 INSTALLING AWS CLI ON WINDOWS

We will be installing AWS CLI version 2.x, the current version intended for use in production environments.


1. Download the AWS CLI MSI installer for Windows (64-bit) at <https://awscli.amazonaws.com/AWSCLIV2.msi>.

Note: In Future to update your current installation of AWS CLI version 2 on Windows, download a new installer each time you update to overwrite previous versions. AWS CLI is updated regularly, so check the [Releases page on GitHub](#) to see when the latest version was released.


2. Run the downloaded MSI installer and follow the on-screen instructions. By default, the AWS CLI installs to **C:\Program Files\Amazon\AWSCLIV2**.
3. Click on Next.



4. Keep install location default and click on Next.




5. Click on Install to start installation.




6. Windows will ask permission to install the so select yes.

7. Wait for the installation to get complete.




8. Installation has been completed click on finish.



9. To confirm the installation, open command prompt (CMD), and use the below command.

```
aws --version
```



```
Command Prompt
Microsoft Windows [Version 10.0.17763.1397]
(c) 2018 Microsoft Corporation. All rights reserved.

C:\Users\retr0>aws --version
aws-cli/2.0.41 Python/3.7.7 Windows/10 exe/AMD64


C:\Users\retr0>
```

Note: If Windows is unable to find the program, and throws an error aws is not recognized as an internal or external command, then try restarting the command prompt and if the error persists then restart whole system so that the changes may take effect.

4 CONFIGURING AWS CLI TO ACCESS AWS SERVICES

1. open a command prompt window
2. To configure the installation, run following command

```
aws configure
```




```
Command Prompt - aws configure
Microsoft Windows [Version 10.0.17763.1397]
(c) 2018 Microsoft Corporation. All rights reserved.

C:\Users\retr0>aws --version
aws-cli/2.0.41 Python/3.7.7 Windows/10 exe/AMD64

C:\Users\retr0>aws configure
AWS Access Key ID [None]: 
AWS Secret Access Key [None]: 
Default region name [None]: us-west-2
Default output format [None]: json
```

Note: By default, all the values are set to null input except default output format.

3. Provide **AWS Access Key ID** from the downloaded CSV file.



```
Command Prompt - aws configure
Microsoft Windows [Version 10.0.19041.508]
(c) 2020 Microsoft Corporation. All rights reserved.

C:\Users\Harshit>aws configure
AWS Access Key ID [None]: AKIAWZP6BXINNATNE3F4
AWS Secret Access Key [None]: 

C:\Users\Harshit>aws configure
AWS Access Key ID [None]: AKIAWZP6BXINNATNE3F4
```


4. Provide **AWS secret access key** from the downloaded CSV file.

```
Command Prompt - aws configure

Microsoft Windows [Version 10.0.19041.508]
(c) 2020 Microsoft Corporation. All rights reserved.

C:\Users\Harshit>aws configure
AWS Access Key ID [None]: AKIAWZP6BXINNATNE3F4
AWS Secret Access Key [None]:

C:\Users\Harshit>aws configure
AWS Access Key ID [None]: AKIAWZP6BXINNATNE3F4
AWS Secret Access Key [None]: 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
```

Note: these are keys specifically associated with an IAM or Root User, they are used to sign programmatic requests that you make to AWS via the CLI.

5. Provide us-east-1 as **Default region name**

```
Command Prompt - aws configure

Microsoft Windows [Version 10.0.19041.508]
(c) 2020 Microsoft Corporation. All rights reserved.

C:\Users\Harshit>aws configure
AWS Access Key ID [None]: AKIAWZP6BXINNATNE3F4
AWS Secret Access Key [None]:

C:\Users\Harshit>aws configure
AWS Access Key ID [None]: AKIAWZP6BXINNATNE3F4
AWS Secret Access Key [None]: RkfCIQWqcxyKdknvzMbJU/xs2M/u4k+pvDdDjghk
Default region name [None]: us-east-1
```

Note: For example, I have typed **us-east-1** to use US East (Virginia).

Note: This identifies the AWS Region whose servers you want to send your requests to by default. This is typically the Region closest to you, but it can be any Region.

6. Select json as **Default output format**.

```
Command Prompt - aws configure
Microsoft Windows [Version 10.0.19041.508]
(c) 2020 Microsoft Corporation. All rights reserved.

C:\Users\Harshit>aws configure
AWS Access Key ID [None]: AKIAWZP6BXINNATNE3F4
AWS Secret Access Key [None]:

C:\Users\Harshit>aws configure
AWS Access Key ID [None]: AKIAWZP6BXINNATNE3F4
AWS Secret Access Key [None]: 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
Default region name [None]: us-east-1
Default output format [None]: json
```

Note: This specifies how the results are formatted. The value can be any of the values in the following list. If you don't specify an output format, json is used as the default.

Note: You have 4 choices for the default output format.

1. json – The output is formatted as a JSON string.
2. yaml – The output is formatted as a YAML string. (Available in the AWS CLI version 2 only.)
3. text – The output is formatted as multiple lines of tab-separated string values. This can be useful to pass the output to a text processor, like grep, sed, or awk.
4. table – The output is formatted as a table using the characters +|- to form the cell borders. It typically presents the information in a "human-friendly" format that is much easier to read than the others, but not as programmatically useful.

7. It will take a few minutes and then drop you back into command prompt.
8. With this your AWS CLI access is setup and ready to go, you can enter a myriad of commands to communicate with each and every AWS service from your command line now.