



ATAK Field Setup

M2 Community Node — Operator Reference

CCC26
LFHI



1. INSTALL APPS

- ATAK-CIV — Play Store (Android only)
- Mumla — Play Store (push-to-talk voice)
- Meshtastic Plugin — GitHub APK (sideload)

2. CONNECT TO SERVER

Option A — Data Package (preferred)

- Join CommunityNode WiFi
- Scan rack QR → tap Open in ATAK
- Login: **field / community**
- Tap OK → server connects automatically

Option B — Manual Entry

- Settings > TAK Servers > Add
- Server: **192.168.8.20** Port: **8089 (SSL)**
- Enroll for cert • uncheck Default SSL
- Cert pwd: **atakatak**

3. SET CALLSIGN

- Settings > My Preferences > Callsign

4. VERIFY

- Your icon appears on the shared map
- Test GeoChat: send a message in #general

CommunityNode WiFi | capableenough.org | v1.0



Voice & Mesh Setup

M2 Community Node — Operator Reference

CCC26
LFHI



MUMLA — PUSH-TO-TALK VOICE

- Server: **192.168.8.20**
Port: **64738 (no password)**
• Open Mumla > Add server > Connect

MESHTASTIC — LORA MESH RADIO

- Install Meshtastic app (Play Store)
- Pair Heltec V3 radio via Bluetooth
- ATAK plugin bridges positions + messages

TROUBLESHOOTING

- No map tiles? Must be on CommunityNode WiFi
- Can't reach server? Disable VPN, Private DNS, firewall
- Cert error? Delete server, re-add from Step 2
- No GPS? Grant location permission, go outside
- Not on map? Set Reporting Strategy to Consistent
- Still not on map? Toggle server off/on in TAK Servers
- Mumla echo? Use headphones or earbuds

REMOTE ACCESS (OFF-NETWORK)

- Web map: **tak.capableenough.org**
• Email OTP login — browser, full shared map
• Remote ATAK: ask operator for VPN access

KEY INFO

- Community page: **192.168.8.10:8081**
• Element chat: #general on capableenough.org
• Clearnet: element.capableenough.org
• Contact: info@capableenough.org

CommunityNode WiFi | capableenough.org | v1.0