Synthetic Window Control

1. Common definitions

Revision QA-WINDOW-20261030. Independent test data, unrelated to operational ICDs.

The simulator represents the controller. All multibyte wire integers are little endian.

No automatic padding, scaling, checksum or trailing bytes are present.

```
SECTION 1 - COMMON DEFINITIONS (outside requested message section)
The common header is 3 bytes and applies to every message:
  Msg: uint8, automatic role id.
  Size: uint8, automatic role length, total bytes including this header.
  Counter: uint8, automatic role seq, maximum 15, scope message, response count.
The enum RunState has exactly Stopped=0 and Running=1.

SECTION 2 - NAMING
Identifiers in the field tables are canonical XML identifiers. Array indexes start at 0.
Use RunState for the Enabled field. Header fields are not repeated in the body.
```

Dependency note: messages on pages 2-3 use this common header and enum.

Message inventory

2. Requested extraction range

Task: define only SET_WINDOW from physical PDF pages 2-3. Follow the common definitions on page 1.

```
Code: SET_WINDOW
Name: Synthetic set window
ID: 0x67
Direction in device documentation: device receives from controller.
Total wire length: 8 bytes. Common header: see section 1.
```

Detailed body layout: page 3. Header roles and RunState values: page 1.

Identifiers are canonical XML identifiers. Array indexes start at 0. Header fields are not repeated in the body.

This inventory does not introduce any additional messages.

Message detail

3. SET_WINDOW

```
SECTION 3 - REQUESTED MESSAGE
Code: SET_WINDOW
Name: Synthetic set window
ID: 0x67
Direction in device documentation: device receives from controller.
Total wire length: 8 bytes. Common header: see section 1.
Body, in exact wire order:
  Limits: uint16, fixed count 2.
  Enabled: uint8, enum RunState.
No Types/Struct declarations are required for this flat body.
```

Common header and enum: page 1. Use the simulator role when converting the device direction.

```
SECTION 4 - SCOPE BOUNDARY
Other device messages are outside this extraction request. Do not invent them.
```