




```
R1
R1#sh ip int br
Interface          IP-Address      OK? Method Status      Prot
-----
Ethernet0/0        172.50.0.1      YES TFTP  up          up
Ethernet0/1        1.0.0.1         YES TFTP  up          up
Ethernet0/2        unassigned      YES TFTP  down        down
Ethernet0/3        unassigned      YES TFTP  down        down

R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip route 62.0.0.0 255.0.0.0 172.50.0.2
R1(config)#ip route 212.25.0.0 255.255.255.0 172.50.0.2
R1(config)#
*Sep  5 13:40:22.017: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R1(config)#ip route 12.0.0.0 255.0.0.0 172.50.0.2
R1(config)#ip route 29.0.0.0 255.0.0.0 172.50.0.2
R1(config)#ip route 222.215.0.0 255.255.255.0 172.50.0.2
R1(config)#ip route 129.23.0.0 255.255.0.0 172.50.0.2
R1(config)#exit
```

```
R2
R2#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#ip dhcp pool sales
R2(dhcp-config)#network 1.0.0.0 255.0.0.0
R2(dhcp-config)#default-router 1.0.0.1
R2(dhcp-config)#dns-server 8.8.8.8
R2(dhcp-config)#exit
R2(config)#ip dhcp excluded-address 1.0.0.1 1.0.0.50
R2(config)#exit
R2#
*Sep  5 14:47:25.263: %SYS-5-CONFIG_I: Configured from console by console
R2#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#ip dhcp pool production
R2(dhcp-config)#network 212.25.0.0 255.255.255.0
R2(dhcp-config)#default-router 212.25.0.1
R2(dhcp-config)#dns-server 8.8.8.8
R2(dhcp-config)#exit
R2(config)#ip dhcp excluded-address 212.25.0.1 212.25.0.50
R2(config)#exit
R2#
R2#
*Sep  5 14:50:59.946: %SYS-5-CONFIG_I: Configured from console by console
R2#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#ip dhcp pool management
R2(dhcp-config)#network 129.23.0.0 255.255.0.0
R2(dhcp-config)#default-router 129.23.0.1
R2(dhcp-config)#dns-server 8.8.8.8
R2(dhcp-config)#exit
R2(config)#ip dhcp excluded-address 129.23.0.1 129.23.0.50
R2(config)#exit
R2#
*Sep  5 14:55:22.016: %SYS-5-CONFIG_I: Configured from console by console
R2#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#ip dhcp pool hr
R2(dhcp-config)#network 29.0.0.0 255.0.0.0
R2(dhcp-config)#default-router 29.0.0.1
R2(dhcp-config)#dns-server 8.8.8.8
R2(dhcp-config)#exit
R2(config)#ip dhcp excluded-address 29.0.0.1 29.0.0.50
R2(config)#exit
```

R3

Sep 6 05:20:40.319: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/0, changed state to down
R3#sh ip int br
Interface IP-Address OK? Method Status Prot
Ethernet0/0 12.0.0.2 YES TFTP up up
Ethernet0/1 29.0.0.1 YES TFTP up up
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down
R3#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#int e0/1
R3(config-if)#ip helper-address 12.0.0.1
R3(config-if)#exit

R4

R4#sh ip int br
Interface IP-Address OK? Method Status Prot
Ethernet0/0 222.215.0.2 YES TFTP up up
Ethernet0/1 129.23.0.1 YES TFTP up up
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down
R4#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R4(config)#int e0/1
R4(config-if)#ip helper-address 222.215.0.1
R4(config-if)#exit
R4(config)#
R4(config)#exit

R1

R1#sh ip int br
Interface IP-Address OK? Method Status Prot
Ethernet0/0 172.50.0.1 YES TFTP up up
Ethernet0/1 1.0.0.1 YES TFTP up up
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#int e0/1
R1(config-if)#ip helper-address 172.50.0.2
R1(config-if)#exit

R5

R5#sh ip int br
Interface IP-Address OK? Method Status Prot
Ethernet0/0 62.0.0.2 YES TFTP up up
Ethernet0/1 212.25.0.1 YES TFTP up up
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down
R5#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R5(config)#int e0/1
R5(config-if)#ip helper-address 62.0.0.1
R5(config-if)#exit

