






HR DEPARTMENT



SALES DEPARTMENT



R1

```
R1(config)#ip dhcp pool HR
R1(dhcp-config)#network 50.0.0.0 255.0.0.0
R1(dhcp-config)#default-router 50.0.0.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 3 4
R1(dhcp-config)#exit
R1(config)#ip dhcp excluded-address 50.0.0.1 50.0.0.60
R1(config)#exit
R1#
*Sep  1 19:20:35.377: %SYS-5-CONFIG_I: Configured from console by console
R1#
R1#show ip dhcp binding
Bindings from all pools not associated with VRF:


| IP address | Client-ID/<br>Hardware address/<br>User name | Lease expiration     | Type      |
|------------|----------------------------------------------|----------------------|-----------|
| 50.0.0.61  | 0100.5079.6668.26                            | Sep 03 2026 03:55 AM | Automatic |
| 50.0.0.62  | 0100.5079.6668.27                            | Sep 03 2026 03:56 AM | Automatic |


R1#
```

```
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#ip dhcp pool SALES
R1(dhcp-config)#network 192.168.2.0 255.255.255.0
R1(dhcp-config)#default-router 192.168.2.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2 5
R1(dhcp-config)#exit
R1(config)#ip dhcp excluded-address 192.168.2.1 192.168.2.60
R1(config)#exit
R1#
*Sep  1 19:29:56.267: %SYS-5-CONFIG_I: Configured from console by console
R1#
R1#show ip dhcp binding
Bindings from all pools not associated with VRF:


| IP address   | Client-ID/<br>Hardware address/<br>User name | Lease expiration     | Type      |
|--------------|----------------------------------------------|----------------------|-----------|
| 50.0.0.61    | 0100.5079.6668.26                            | Sep 03 2026 03:55 AM | Automatic |
| 50.0.0.62    | 0100.5079.6668.27                            | Sep 03 2026 03:56 AM | Automatic |
| 192.168.2.61 | 0100.5079.6668.28                            | Sep 03 2026 03:16 AM | Automatic |
| 192.168.2.62 | 0150.ae34.0911.00                            | Sep 03 2026 03:17 AM | Automatic |


```

```
R2#conf t
```


```
Enter configuration commands, one per line. End with CNTL/Z.
```

```
R2(config)#int e0/0
```

```
R2(config-if)#ip helper-address 172.16.0.1
```

```
R2(config-if)#exit
```

```
R2(config)#
```



```
VPC-1

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-1> ip dhcp
DDORA IP 50.0.0.61/8 GW 50.0.0.1

VPC-1> █
```

VPC-2

```
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.


VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-2> ip dhcp
DDORA IP 50.0.0.62/8 GW 50.0.0.1

VPC-2> █
```



The image shows a window titled "VPC-4" with a standard Windows-style title bar (minimize, maximize, close buttons). The window contains a black terminal area with white text. The text displays the welcome message for the Virtual PC Simulator, version 1.3 (0.8.1), dedicated to Daling. It includes build time information (May 7 2022 15:27:29) and copyright notices for Paul Meng (2007-2015) and Alain Degreffe (2021). The text also states that VPCS is free software under the BSD license, with source code and license available at vpcs.sf.net and more information at wiki.freecode.com.cn. It mentions a modified version for EVE-NG. The prompt "Press '?' to get help." is shown. Below that, it says "Executing the startup file". The terminal then shows the command "VPC-4> ip dhcp" and the response "DDORA IP 192.168.2.61/24 GW 192.168.2.1". Finally, it shows "VPC-4> " followed by a red cursor.

```
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-4> ip dhcp
DDORA IP 192.168.2.61/24 GW 192.168.2.1

VPC-4> █
```

