




Module 05

Group User Accounts and Disk Quota





1. Group User Accounts

- 1.1. What is Group
- 1.2. Type of Groups
- 1.3. Basic Build-in Group
- 1.4. Create a Group
- 1.5. Add User to Group
- 1.6. Remove Group from User
- 1.7. Add Group to User




2. Disk Quota


- 2.1. Configure Disk Quota for a User
- 2.2. Configure Disk Quota for all Users



1. Group User Accounts



1.1. What is Group?



Group User Accounts is a collection of different user accounts combined into a single group. It makes it easier for us to assign permissions and rights to a group of users directly, taking less time than assigning permissions and rights to individual users. Each user can be a member of more than one group.



Group User Accounts are divided into two categories:

Build-in Group: assign right or privilege

Custom Group: to assign permissions when sharing data

1.2. Type of Groups

- In terms of using the data on the server, the administrator can assign permissions to each Group User Accounts to have different permissions according to different roles and requirements, including:
 - Domain Guest: The lowest privileged group of User Accounts, using only data, cannot install software or modify settings on the machine, and usually this group is closed after Setting up Active Directory.

1.2. Type of Groups (Cont.)

- Domain Users: is a Group User Account that has certain privileges, such as the ability to run other programs, have access to printers and data, and is automatically created when creating a new account.
- Domain Admins: is a Group User Account that has full rights to use and manage the server, can create, delete and manage everything in the domain, especially can change the password to the user and manage all services in the network.

1.2. Type of Groups (Cont.)

- Server Operator: is a Group User Account that has the right to manage the server, such as data sharing, set some Services to run can Backup and Restore data or format a hard disk.
- Account Operator is a Group User Account that has the right to manage and control the entire account, such as creating, deleting, editing user accounts, etc., but cannot change the Administrator Password.
- Backup Operator: is a Group User Account that has the right to backup and restore data on the server.

1.2. Type of Groups (Cont.)


- Print Operators is a Group User Account that has the right to manage the printer.
- Replicator (legacy / rarely used in modern environments): is a Group User Account that has the right to implement Active Directory replication between domain controllers.

1.3. Basic Built-in Group

- There are many types of Group Accounts in the Built-in Group, and the easy-to-use Built-in Group includes Domain Admin and Domain Users.
 - Users in the Domain Administrator have full access to and control of the server.
 - Users in the Domain Users are only allowed to use. By default, the account or user we created is a member of the Domain Users Group.


1.4. Create a Group

- Step 1: Click **Tools** menu > **Active Directory Users and Computers** > Under an OU, right click and select **New** > **Group**



1.4. Create a Group (Cont.)

- Step 2: In **Group name** text field, type **Group name (IT)** > Click **OK**



New Object - Group

Create in: makara.com/IT Dept

Group name:
IT

Group name (pre-Windows 2000):
IT

Group scope

- ☐ Domain local
- ☒ Global
- ☐ Universal



Group type

- ☒ Security
- ☐ Distribution

OK Cancel



1.5. Add User to Group

- Step 1: Right click on a **Group** > Select **Properties** > on Tab Members > Click **Add** button





1.5. Add User to Group (Cont.)

- Step 2: type **Username** (Ex: 13052) > Click **Check Names** button > Click **OK**





1.5. Add User to Group (Cont.)

- Step 3: Click **Apply** > Click **OK**






1.6. Remove Group from User

- Step 1: Right click on a user > Click Properties > Select Member Of tab





1.6. Remove Group from User (Cont.)

- Step 2: Select a group you want remove (IT) > Click Remove button > Click Yes button > OK





1.7. Add Group to User

- Step 1: Right click on a user > Select **Properties** > Select **Member Of** > Click **Add** button





1.7. Add Group to User (Cont.)

- Step 2: type **IT** in text area > Click **Check Names** button > Click **OK**



1.7. Add Group to User (Cont.)

- Step 3: Click **Apply** > Click **OK**







2. Disk Quota




2.1. Configure Disk Quota for a User

- Step 1: Right-click the selected **drive (C:)** > Select **Properties** > Click **Quota** tab > Check **Enable quota management** and **Deny disk space to users exceeding quota limit** > Click **Quota Entries**




2.1. Configure Disk Quota for a User (Cont.)

- Step 2: Click **New** icon > type **username** (Ex: **13052**) and click **Check Names** button > Click **OK** > Select **Limit disk space to** and enter number of file size to limit (1024 MB) and **Set warning level to** (1000 MB) > OK





2.1. Configure Disk Quota for a User (Cont.)

- Step 3: **Close Quota Entries** windows > Click **Apply**
- Step 4: Click **OK** > Click **OK**





2.1. Configure Disk Quota for a User (Cont.)

- Step 5: On Windows Client **Login** with configured user > Right click on configured **quota drive** > Select **Properties**





2.1. Configure Disk Quota for a User (Cont.)

- Step 6: You can see the result of quota configuration on **Capacity** section
- Step 7: If you store new file on **quota drive** more than **limitation**, it will **show error message** as below





2.2. Configure Disk Quota for all Users

- Step 1: Right-click the selected **drive (C:)** > Select **Properties** > Click **Quota** tab > Check **Enable quota management** and **Deny disk space to users exceeding quota limit**





2.2. Configure Disk Quota for all Users (Cont.)

- Step 2: Select **Limit disk space to** and enter number of file size to limit (100 MB) and **Set warning level to** (99 MB) > Click **Apply** > Click **OK**




2.2. Configure Disk Quota for all Users (Cont.)


- Step 3: **Login** with configured user > Right click on configured **quota drive** > Select **Properties**



2.2. Configure Disk Quota for all Users (Cont.)

- Step 4: You can see the result of quota configuration on **Capacity** section





Thank You.