        - SAP Extended Warehouse Management
        - SAP Transportation Management
    - **SAP ERP Location**: Locations from an SAP ERP system
    - **Others**: Locations from other systems
- **Location Type**: Type of the location

  This field is available when **Source** is set to **SAP SCM Logistic Location**.
- **Object Type**: Business purpose of a location.

  This field is configurable when **Source** is set to **SAP ERP Location** or **Others**. When **Source** is set to **SAP SCM Logistic Location**, the system automatically sets **Object Type** to **Logistic Location**.

  Valid values for the Object Type field are::

    - **Business Partner**
    - **Customer**
    - **Plant**
    - **Shipping Point**
    - **Supplier**

  If none of the values above fits the location's business purpose, you can change **Source** to **SAP SCM Logistic Location** as an alternative. This will set **Object Type** to **Logistic Location** at the backend and make **Location Type** configurable. The **Location Type** field provides you with a broader list of types pertaining to various business purposes, such as port and hub.

  > **Note**
  >
  > You can also maintain the information of an ordering party in this app by setting the **Object Type** field to **Business Partner**.

- **Description**: Descriptive information about the location
- **Source System/External ID**: Source system from which the location master data is copied and the corresponding ID.
    - If you are creating a location from scratch, set the **Source System** part to LBN, and set the **External ID** part to the location ID you previously prepared.
    - If you are importing a location from SAP Transportation Management (TM), set the **Source System** to the business system name of your TM system and set the **External ID** to the location ID in TM.

      For locations that have its object type set to "Business Partner", you can find the business system name of your TM system and the location ID in the SOAP request message sent to LBN. In this request, the *MessageHeader.SenderBusinessSystemID* attribute specifies the business system name and the internal ID of the sender (the *MessageHeader.SenderParty.InternalID* attribute) specifies the location ID.

      Alternatively, you can run transaction code *SLDCHECK* in TM to view the business system name.
    - **Logical System**: You can also use the **Logical System** field to identify the system from which the location master data is replicated.

      The **Logical System** field is is optional in SAP Business Network Freight Collaboration. If you've only purchased the freight collaboration solution, leave this field empty. If you've purchased both freight collaboration and global track and trace, refer to the configuration for global track and trace to maintain the logical system ID.
- (Optional) **Address**:

        - **Country/Region**
        - **State**
        - **City**
        - **District**
        - **Street/House Number**
        - **Zip Code**
    - (Optional) **Geographical Coordinates And Map**:
        - **Longitude**: Longitude coordinate of the location
        - **Latitude**: Latitude coordinate of the location

        > **Note**
        >
        > You can enter the coordinates in the **Longitude** and **Latitude** fields manually. If you want the system to verify your entries, set **Calibrate coordinates when saving** to **Yes** before you save your changes. You can also choose **Generate Longitude and Latitude Coordinates** to create the coordinates according to the address information you've entered.
        >
        > By default, **Calibrate coordinates when saving** is set to **Apply global settings**, meaning that how the system handles coordinates for the location record you are working on is determined by the option you choose in the **Generate geo-coordinates automatically** setting, which can be found in the **Settings** dialogue box. If you leave **Generate geo-coordinates automatically** with the default option, the system generates geo-coordinates for locations when both the latitude and longitude coordinates are missing. For more information, see Global settings for Geo-Coordinates.

    - (Optional) **Time Zone**
    - (Optional) **Alternative Location ID**:
        - **Type**: Type of the alternative ID.
        - **ID**: Alternative ID in the specified type.
    - (Optional) **Contact Information**: Contact information related to the location.
    - (Optional) **Additional Information**: Additional information about the location. For more detail, see Define Additional Information.

3. Choose **Save**.

### Result

The newly-created location master data can be consumed by other apps in SAP Business Network Freight Collaboration. For example, when defining the settings for a docking location in Docking Location Settings, you must associate the docking location with a location created in Manage Locations.

## Upload Locations

You can fill the details of locations using an Excel template and then upload this template back to the app. To do this, follow these steps:

1. Choose **Upload** to open the **Upload Locations** page.
2. Click **Upload** on the up-right corner, then download the Excel template available by choosing **Download Excel Template**.
3. Fill the details of the locations you want to upload in the template.

4. In **Choose File**, locate the modified Excel template and then choose **Upload**.

### ℹ Note

You can enter the geographical coordinates for the location records in the **Longitude** and **Latitude** columns manually. If you want the system to verify your entries, set **Calibrate coordinates when saving** to **Yes** before you upload your file.

By default, **Calibrate coordinates when saving** is set to **Apply global settings**, meaning that how the system handles coordinates for the location records you are uploading is determined by the option you choose in the **Generate geo-coordinates automatically** setting, which can be found in the **Settings** dialogue box. If you leave **Generate geo-coordinates automatically** with the default option, the system generates geo-coordinates for locations when both the latitude and longitude coordinates are missing. For more information, see Global settings for Geo-Coordinates.

# Editing a Location

To edit a location, proceed as follows:

1. Use the following fields to filter locations:
    - Location ID
    - Description
    - Location Type
    - Country/Region
    - City
2. Click the location from the filter results to open the details page.
3. Choose **Edit** on the upper-right corner of the details page.

# Viewing a Location

To view a location, proceed as follows:

1. By default, you can use the following fields to filter locations:
    - External ID
    - Source System
    - Object Type
    - Description
    - Country/Region
    - City
    - Data Processing Status
    - Additional Information

    You can also adjust the filter bar by chooosing **Adapt Filters**.
2. Click the location from the filter results to open the details page.

The detail view of the location consists of a header and other sections.

## Header

The Header section displays the address information.

## General

This section displays the basic information of a location. This includes the business purposes, the longitude/latitude coordinates, and the revision history.

## Geographical Coordinates and Map

This section displays the geographical coordinates of the location. It also identifies the location on the map.

## Alternative Location IDs

This section displays a list of type-specific alternative IDs of the location.

## Contact Information

This section displays the contact information related to the location.

## Additional Information

This section displays the contact information related to the location.

## More Information

You can do the following with the filter bar:

- Specify filters to narrow down the worklists and search for locations.
- Add or remove the filters displayed on the filter bar by choosing **Adapt Filters**.
- Save the current filter settings as a view and apply it later.

  After you specified filters (and pressed Enter) and/or adapted filter display, the current view name shown in the upper-left corner displays a * sign, indicating the view has been changed. Save the view by either of the following:

  - Click the view name to open the **My Views** box and choose **Save** or **Save As**.
  - In the **Adapt Filters** dialog box, choose **Save**.

  Next time when you want to apply the view, just select the view name in the **My Views** box.

  **Note**

  The default **Standard** view cannot be changed.

# Define Additional Information

The Additional Information section contains a list of additional information associated to a location record. This section enables you to define necessary custom characteristics or references by adding your information items.

An information item comprises a name, the type of the item, and the corresponding value.

- **Type**: Type of the additional information item. It can be either **Text** or **Alternative ID**.
- **Name**: Name of the additional information item. If you set **Type** to **Alternative ID**, the name of the item must be set to one of the following values:
    - GLN
    - DUNS
    - UN/LOCODE
    - IATA Airport Code
- **Value**: Value that corresponds to this additional information item.

# Manage Custom Codes

You can use the manage custom codes feature to extend the drop-down list for the following fields:

- Country/Region
- State
- Location Type
- Time Zone
- Role of Contact

This feature is useful if the drop-down list of a field does not contain the code you want to select. For example, you do not find the region code you need in the drop-down list of **Country/Region**.

To create a custom code, proceed as follows:

1. Choose the **Manage Custom Codes** button.
2. On the **Manage Custom Codes** page, select the field for which you want to extend the list, and then choose **Create**.
3. Specify the name, language, and description of the code, and then choose **Save**.

## Results

After you create a custom code, you can find it from the **Custom** category when you expand the corresponding drop-down list. If needed, you can also remove it or edit its description on the **Manage Custom Codes** page.

# Global settings for Geo-Coordinates

You can use **Generate geo-coordinates automatically** in the **Settings** dialogue box to define how the system handles geo-coordinates for all location records. In **Generate geo-coordinates automatically**, you have the following options:

- **Off** (Default): Do not generate geo-coordinates automatically even if they are missing.
- **Generate**: Generate geo-coordinates for locations when both the latitude and longitude coordinates are missing. (Applies to all locations including the existing ones)
- **Overwrite**: Generate geo-coordinates for locations when coordinates are missing or overwrite them if they already exist. (Applies to locations created after you enable this option)

### ℹ Note

- Options in **Generate geo-coordinates automatically** only take effect for location records where you leave **Calibrate coordinates when saving** with the default option **Apply global settings**.
- The **Calibrate coordinates when saving** setting in location records takes precedence over **Generate geo-coordinates automatically** in the **Settings** dialogue box. For example, when you set **Calibrate coordinates when saving** to **No** in a location record, the system does not generate or calibrate coordinates for the record even if **Generate geo-coordinates** automatically is set to **Generate** or **Overwrite**.

# Archiving Locations

If you have location records that are no longer used regularly, you can archive these records for future reference or regulatory compliance.

### ℹ Note

To archive locations, you must have the LocationArchiveTemplate role.

To archive location records, select the records you want to archive on the **Locations** list and then choose **Archive**. You can view the locations you've archived on the **Archived Locations** list by choosing **Archived Items** at the up-right corner.

To restore archived location records, select the records you want to restore on the **Archived Locations** list, and then choose **Restore**. You can view the restored locations after you switch to the standard **Locations** list.

# Enable Risk Monitoring

If you have configured the risk monitoring service provider in Configure Partner Connections, you can determine whether or not to use the service provider to monitor risks at a certain location in Manage Locations.

### ℹ Note

Risk information is not displayed in Manage Locations. Instead, it's displayed on the map view of the Logistics Execution Insights app. You use Manage Locations to specify a group of target locations where you want to monitor risks.

## Prerequisites

You have configured the risk monitoring service provider in Configure Partner Connections.

## Procedure

To enable risk monitoring for a specific location, follow these steps:

1. Click the location record for which you want to monitor risks to open its details page.
2. Choose **Edit** on the upper-right corner.
3. Click to select the **Enable supply chain risk monitoring** checkbox and then choose **Save**.

### ℹ Note

You can also configure this setting when creating a new location record.

Alternatively, you can enable risk monitoring for multiple locations at once. To do this, select the location records, and then choose **Risk Monitoring** > **Enable**.

### Results

The risk monitoring service provider starts monitoring risks at the location. If you've subscribed for the intelligent insights add-on, you can view the risk information on each target location in the Logistics Execution Insights app.

To notify the service provider to stop monitoring risks at a location, uncheck the **Enable supply chain risk monitoring** checkbox in the corresponding location record.

To stop using the risk monitoring feature for all locations in your supply chain, uncheck the **Enable supply chain risk monitoring** checkbox in each location record where you previously enabled the feature in Manage Locations and then deactivate the risk monitoring service provider in Configure Partner Connections.

### More Information

Editing a Location

Creating a Location

## Define User Settings (Shipper)

The **Define User Settings** app allows you to define defaults that best suit the way you work.

### Prerequisites

To use this app, you must add one or several roles to your role collection. The required role templates and application identifiers are described in the Available Roles for Shippers section of the Administration Guide for Shippers.

### Notification Subscriptions

In this section, you can subscribe to notifications for various scenarios and specify the email address and preferred language for receiving the notifications. Note that you cannot subscribe to a scenario without maintaining an email address.

When you subscribe to notifications for a scenario, the system can send email notifications based on the settings you make in the **Manage Notification Settings** app.

For more information on managing notification settings, see Manage Notification Settings (Shipper).

## Manage Notification Settings (Shipper)

You can use this app to schedule reminder notifications for some of the business processes for which you may need an alert.

The system sends you notifications via emails.

The **Manage Notification Settings** app consists of the following areas:

- List of scenarios

This area displays the scenarios for which you can configure alerts.

- Filter

  You can use this filter to filter the scenarios. When you select a scenario from this drop-down menu, the system displays only that specific scenario.

- Configuration details

  The system displays the following in this area:

  - Configurations

    The system displays types of notifications and the settings that you can configure for each type.

  - Subscribers

    The system displays the list of users who have subscribed to notifications for the current scenario. The subscription is made in the **Define User Settings** app.

## Scenarios

As a shipper, you can schedule email notifications for the following scenarios:

| Scenario Group | Scenario | Description |
|---|---|---|
| Business Operations | Integration Error V2 | The system now sends an email notification to you when an integration error occurs. |
| Dock Appointment Scheduling | Create Appointment | For receiving email notification when a dock appointment has been created by a carrier. |
| | Cancel Appointment | For receiving email notification when a scheduled dock appointment has been canceled by the carrier. |
| | Update Appointment | For receiving email notification when a dock appointment has been rescheduled by the carrier. |
| Freight Booking Management | Confirm Freight Booking | The system sends an email notification when a carrier confirms a freight booking. |
| | Reject Freight Booking | The system sends an email notification when a carrier rejects a freight booking. |
| Freight Order Management | Confirm Freight Order | The system sends an email notification to you when the carrier confirms a freight order or a freight order with the document category as **Shipment**. |
| | Reject Freight Order | The system sends an email notification to you when the carrier rejects a freight order or a freight order with the document category as **Shipment**. |
| Freight Settlement | Update Shipper Dispute | The system sends an email notification to you when a dispute document is created or updated for your review. The notification email includes a link to the dispute document. |

| Scenario Group | Scenario | Description |
|---|---|---|
| | Resolve Shipper Dispute | The system sends an email notification to you when the carrier resolves a dispute document. The notification email includes a link to the dispute document. |
| | Pending Invoice Submitted | The system sends an email notification to you when the pending invoice document from your carrier has been submitted after receiving the corresponding freight document in SAP Business Network for Logistics. |
| | Invoice Submission Pending | The system sends an email notification to you when the invoice document from your carrier is not yet submitted as the corresponding freight document is not available in SAP Business Network for Logistics. |
| Manage Network | Certificate Expiry | The SAP Cloud Platform Integration (CPI) certificate is maintained in the **System Connections** app to enable the connection from your system to your SAP Business Network for Logistics system. When the certificate expires, you must renew it by deleting the old certificate and adding a new one in the **System Connections** app.<br><br>You can schedule alerts for the expiry of CPI certificate by specifying the following settings:<br><br>• On-Event Notification<br><br>Specify whether you want to receive an email notification at the time when the CPI certificate expires.<br><br>• Pre-Event Notifications<br><br>Specify whether you want to receive email notifications before the expiry of the CPI certificate, and configure the notification schedule.<br><br>• Post-Event Notifications<br><br>Specify whether you want to receive email notifications after the expiry of the CPI certificate, and configure the notification schedule. |
| Freight Tracking | Exception Event | The system sends an email notification to you when an exception event is reported. |

### Note

To enable the above notifications, you need to activate the settings in this app and subscribe to notifications for the certificate expiry scenario in the **Define User Settings** app.

As of now, the system displays up to 5000 characters on the subject line of the reminder notification email. However, in some scenarios, the subject line may get truncated due to the limitations from your mail clients such as Microsoft Outlook or Google Mail.

## Related Information

Define User Settings (Shipper)

# Configure Notification Settings (Shipper)

## Prerequisites

To enable reminder notifications, make sure you also maintain an email address and subscribe to the notification(s) you need in the **Define User Settings** app. For more information, see Define User Settings (Shipper)

## Context

You can configure the following types of notifications in the **Manage Notification Settings** app, where applicable.

### On-Event Notification

On-event notification refers to the email notification that you receive at the time when a target event happens, for example, when your SAP Cloud Platform Integration (CPI) certificate expires. You can activate or deactivate on-event notification by setting the activation toggle to **Yes** or **No**, respectively.

### Pre-Event Notifications

Pre-event notifications refer to the notifications you receive before the target event happens, for example, before your CPI certificate expires. You can schedule pre-event notifications by adding notification periods and specifying notification frequency within each period, as described below:

- Notification period: The period within which email notifications will be sent in a specified frequency.

  You only specify the start of the period, for example, **30 days before the event**, which means the notification period starts from 30 days before the event till the start of the next period or the event time.

- Frequency: The frequency to receive notifications within the specified period. For example, setting the frequency to **every 5 days** means within the specified period, you'll receive an email notification every 5 days.

### Example

The schedule shown below

| Notification Period | Frequency | Activated for User |
|---|---|---|
| 60 days | Every 10 days | Yes |
| 30 days | Every 5 days | Yes |
| 15 days | Every 3 days | Yes |

specifies the following schedule:

- Within the period from 60 days before the event to 30 days before the event, receive a notification every 10 days.