- Incoterm
- Incoterm Location
- Latitude
- Lifecycle Status
- Logical System
- Longitude
- Master Ocean Bill of Lading
- Means of Transport
- Movement Type
- Next Stop
- Number of Loading Stops
- Number of Unloading Stops
- Number of Visits
- Planned Arrival At
- Planned Arrival Date
- Planned Arrival Time Zone
- Planned Departure At
- Planned Departure Date
- Planned Departure Time Zone
- Planned Gross Duration
- Planned Net Duration
- Planned Total Distance
- Planned Total Distance UoM
- Registration Country or Region / Number
- Shipper External ID
- Shipper LBN ID
- Shipping Type
- Source Location
- Traffic Direction
- Transportation Mode
- Vehicle
- Vessel

Freight Document Attributes

The following table provides descriptions of the attributes that can be displayed in the **Freight Documents** list. Some attributes are also shown in the freight document detailed view.

Field	Description
Cargo Quantity	Cargo quantity of a freight document
Cargo Quantity UoM	Unit of measure of cargo quantity
Cargo Volume	Cargo volume of a freight document
Cargo Volume UoM	Unit of measure of cargo volume
Cargo Weight	Cargo weight of a freight document
Cargo Weight UoM	Unit of measure of cargo weight
Carrier External ID	Carrier identifier in an external system such as SAP TM
Dangerous Goods	An indicator that shows whether the cargo contains substances and objects that are a threat to humans, animals, or the environment when they are transported
Destination Location	The last arrival location of a freight document
Estimated Arrival At	The time when a freight documennt is expected to arrive at a specified stop
Estimated Arrival Time Zone	The time zone of the date and time for arrival at a specified stop
Incoterm	An international commercial term that defines the terms of sales and the passing of risks for import and export of merchandise. Incoterm is published by the International Chamber of Commerce (ICC) and widely used in commercial transactions.
Incoterm Location	A geographical location (harbor name, railway station name, transfer-cargo-terminal name, and so on) that is entered in conjunction with an Incoterm to uniquely identify the point from which the division of costs and transfer of risks are assumed between two commercial parties (purchaser and seller).
Latitude	Latitude of the current position of a freight document
Lifecycle Status	When you create a freight document, the lifecycle status of the document is **Active**. When the execution status becomes **Executed**, the lifecycle status of the document changes to **End of Business**, which means the retention period starts. When the retention period is over, the lifecycle status changes to **End of Purpose**, which means the blocking period starts. When the blocking period is over, the freight document will be deleted. The length of residence period and blocking period can be specified in the **Retention Management** app. For more information, see Retention Management
Longitude	Longitude of the current position of a freight document
Means of Transport	Category of vehicle resources, for example, container ships or cargo ships

Field	Description
Next Stop	The next stop that a freight document is expected to arrive at
Number of Loading Stops	Number of the stops with planned loading events
Number of Unloading Stops	Number of the stops with planned unloading events
Number of Visits	Number of the stops that a freight document is expected to visit
Planned Arrival At	The planned date and time when a freight document is expected to arrive at the last stop (in the Freight Documents list page) or a specified stop (in the details view)
Planned Arrival Date	The planned date when a freight document is expected to arrive at the last stop (in the Freight Documents list page) or a specified stop (in the details view)
Planned Arrival Time Zone	Time zone of planned arrival date and time
Planned Departure At	The planned date and time when a freight document is expected to depart from the first stop (in the Freight Documents list page) or a specified stop (in the details view)
Planned Departure Date	The planned date when a freight document is expected to depart from the first stop (in the Freight Documents list page) or a specified stop (in the details view)
Planned Departure Time Zone	Time zone of planned departure date and time
Planned Gross Duration	The duration between the business date and time of the first and the last planned events in a freight document
Planned Net Duration	Total planned travel time of a freight document
Planned Total Distance	Total distance of a freight document
Planned Total Distance UoM	Unit of measure of planned total distance
Registration Country/Region	The country/region where a vehicle in a freight document is registered
Registration Number	Registration plate number of a vehicle in a freight document
Shipper External ID	Shipper identifier in an external system such as SAP TM
Shipper LBN ID	Shipper identifier in SAP Business Network for Logistics
Shipping Type	An attribute that specifies how the transportation of cargo is planned and executed. Examples of shipping types are full container load (FCL) and less than container load (LCL).
Source Location	The planned stop where a freight document is expected to depart firstly
Traffic Direction	An object that specifies if cargo is being imported or exported from the perspective of the contracting party
Vehicle	A means of transport or a group of identical means of transport that can provide transportation services
Ocean Bill of Lading	A document required for ocean shipments to transport goods internationally

Field	Description
Mode of Transport	Category of transportation, for example, road, ocean, air, and so on
Vessel ID	ID of the vessel in ocean shipments
Voyage Number	A unique identifier of the voyage in ocean shipments.
Movement Type	An attribute that specifies the stages for which a logistics service provider (LSP) or carrier is responsible. For example, door-to-door, port-to-port, and so on.
Container IDs	Identification number of a container, generally as per a standard container identification system (for example, ISO 6346)
IMO Ship Identification Number	The International Maritime Organization (IMO) number is a unique identifier assigned to propelled, seagoing vessels of 100 gross tons and above. It consists of the three letters "IMO" followed by unique seven-digit numbers.

Execution Status, Process Status, and Event Status

The following describes the concepts of execution status, process status, and event status of a freight document.

Execution Status

Execution status shows the execution progress of a freight document. See the below table for status description.

Execution Status	Description
Ready for Execution	When a freight document is set to ready for transportation execution in your SAP TM or SAP S/4HANA system, the execution status is Ready for Execution in the Track Freight Movement app. This is the original execution status of a freight document.
Execution Started	When the visibility provider reports an event at the source location, the execution status changes to Execution Started.
In Transit	When the visibility provider reports a departure, the execution status changes to In Transit.
Arrived at Intermediate Location	When the visibility provider reports an arrival at an intermediate location, the execution status changes to Arrived at Intermediate Location.
Arrived at Destination	When the visibility provider reports an arrival at the destination location, the execution status changes to Arrived at Destination.
Executed	When the visibility provider reports an event that matches the last expected event, for example, arrived at destination, configured in your SAP TM or SAP S/4HANA system, the execution status changes to Executed.

Process Status

The Track Freight Movement app tracks business process for each freight document. The status of business process is determined by the status of the most recently occurred event within the process. See the below table for process status description.

Process Status	Description
As Planned	The original status of a process.
Early	When an actual event is reported to occur earlier than the expected time window*, the process status changes to Early.
Late	When an actual event is reported to occur later than the expected time window*, the process status changes to Late.
Overdue	When the expected time window* for a planned event is overdue, but no actual event has been reported, the process status changes to Overdue.
Delayed	When a Delay event is reported, the process status changes to Delayed.

* The expected time window is a time period between the earliest and latest expected business or technical date and time. By default, the earliest time is 10 minutes before the planned event time and the latest is 10 minutes after the planned event time. If you want to change the default, contact your system administrator to maintain SAP BAdI /SCMTMS/TOR_SE_TRCKPR_OUT.

Event Status

The Track Freight Movement app tracks business process for each freight document, and the business process includes planned and unplanned events. Each event has a status, as described below.

Event Status	Description
Planned	The original event status.
Reported On Time	The event has been reported and the reported event time is within the expected time window*.
Reported Early	The event has been reported and the reported event time is earlier than the expected time window*.
Reported Late	The event has been reported and the reported event time is later than the expected time window*.
Overdue	When there is no actual event reported within the expected time window* for a planned event, the event status changes to Overdue.
Delayed	When it is estimated that a planned event cannot be executed on time, a Delay event can be reported as a reference to the original planned event, and the status of the original event changes to Delayed. The Delay event itself is shown in the execution flow and map view with the event status Unplanned. If the delay is dismissed, which means the expected event can be executed on time based on new estimation, then the status of the original event changes from Delayed back to Planned, and the status of the Delay event changes from Unplanned to Dismissed.

* The expected time window is a time period between the earliest and latest expected business or technical date and time. By default, the earliest time is 10 minutes before the planned event time and the latest is 10 minutes after the planned event time. If you want to change the default, contact your system administrator to maintain SAP BAdI /SCMTMS/TOR_SE_TRCKPR_OUT.

Detailed View (Track Freight Movement)

From the **Freight Documents** list, you can navigate to the freight document details. The detailed view consists of a header and several sections.

Header

The header displays the following information about the freight document:

- **Freight Document ID**
- **Freight Document Type**
- **Execution Status**

  Displays the execution progress of a freight document. Displays one of the following statuses:

  - **Ready for Execution**
  - **Execution Started**
  - **In Transit**
  - **Arrived at Intermediate Location**
  - **Arrived at Destination**
  - **Executed**

  For more information on execution status, see Execution Status, Process Status, and Event Status.

- **Process Status**

  Displays whether the freight execution is **As Planned**, **Early**, **Late**, **Overdue**, or **Delayed**. The system shows **Early**, **Late**, **Overdue** and **Delayed** statuses with a warning sign on the header. The status changes according to the **most recently** reported event or the **most recently** triggered overdue event.

  For more information on process status, see Execution Status, Process Status, and Event Status.

- **Source Location**, **Destination Location**, and **Next Stop**

  Displays the source location, destination location, and next stop of a freight document.

  The source location displays the following details:

  - **Location**
  - **Address**
  - **Planned Departure At**
  - **Actual Departure At**

    Note that the system displays this information only when the actual departure date and time has been reported.

  - **Estimated Departure At**

  The destination location displays the following details:

  - **Location**
  - **Address**
  - **Planned Arrival At**

- **Actual Arrival At**

  Note that the system displays this information only when the actual arrival date and time has been reported.

- **Estimated Arrival At**

The next stop displays the following information:

- **Location**
- **Planned Arrival At**

  Note that if the planned and estimated arrival date and time has been reported, the system displays the planned arrival date and time for the next stop along with the calculated delay or earliness of arrival. The calculated delay or earliness of arrival is the difference between the estimated arrival and the planned arrival.

- **Estimated Arrival At**

  Note that if only the estimated arrival date and time has been reported and the planned arrival date and time has not been reported, the system displays the estimated arrival date and time for the next stop.

When you choose the location, the system displays the additional details of the location. You can also view the latitude and longitude details of the location by choosing the globe icon.

> **Note**
> You can view the **Next Stop** information also for tracking requests that are yet to be executed. The system receives this information from the freight document in SAP Transportation Management system.

- **Events by Status** pie chart

  Displays the proportion of planned events, exceptional events, and events reported on time. The system displays the following statuses:

  - **Planned**
  - **Reported On Time**,
  - **Reported Early**
  - **Reported Late**
  - **Overdue**
  - **Delayed**

  The system categorizes the events in the pie chart as follows:

  - Events with the status as **Planned** are categorized as **Planned**
  - Events with the status as **Reported Early**, **Reported Late**, **Overdue** and **Delayed** are categorized as **Exceptional**
  - Events with the status as **Reported On Time** are categorized as **Reported On Time**

  For more information on event status, see Execution Status, Process Status, and Event Status.

Information

This section displays the following information:

- **General Data**
  - **Carrier**
  - **Ocean Bill of Lading**

    - Means of Transport
    - Mode of Transport
- Terms and Conditions
    - Incoterm
    - Incoterm Location
    - Movement Type
    - Shipping Type
    - Traffic Direction
- Cargo Information
    - Cargo Weight
    - Cargo Volume
    - Cargo Quantity
    - Container IDs
    - Dangerous Goods
- Voyage
    - Voyage Number
    - Vessel ID
    - IMO Ship Identification Number
- Transportation
    - Planned Total Distance
    - Planned Gross Duration
    - Planned Net Duration
    - Number of Visits
    - Number of Loading Stops
    - Number of Unloading Stops

For more information on the descriptions of the data, see Freight Document Attributes.

Execution Flow

Displays the visual representation of the execution flow with the source location, stops, and destination location.

In the graphic, each circle represents a stop with an icon indicating the type. You can see the legend in the map view to learn more.

The color of a circle is defined as follows:

- Green: Indicates the proportion of events with status **Reported On Time**
- Yellow: Indicates the proportion of events with status **Delayed**, **Overdue**, **Reported Early**, **Reported Late** or **Unplanned**
- Grey: Indicates the proportion of events with status **Planned** or **Dismissed**

Beneath each stop circle, a graphic of one card or overlapping cards are shown, indicating one or multiple events occurred at the stop. Each card displays the information for the earliest planned event or the most recently occurred status-changing event. You can click the card to view all the planned and reported events at the stop. The system displays the location and planned date and time for each of these events. You can also view the estimated date and time (if reported) and the actual date and time (if reported). Note that once the actual time is reported, the system does not display the estimated date and time. The card for the next stop shows the planned and estimated time of arrival (if reported) at the stop.

The lines between cards show the time duration for transporting goods between the two stops, if the transportation has already happened, which means, the departure event of the former stop and the arrival event of the latter stop have been reported. You can click a line to view all the planned and reported events on the shipping route. You can view the actual events on unplanned stops reported by the carrier though API.

Map View

The map view allows you to monitor the following of a freight document.

- Locations

  The following types of locations are displayed on the map with different icons as shown in the map legend. If the legend doesn't appear, click the legend icon to show it.

Location Type	Description
Source	The first stop where the freight document execution starts
Intermediate Stop	The stops between the source and destination locations where planned or unplanned events occur
Destination	The last stop where the freight document execution ends
Current	The location where an event was most recently reported
Event	The location where planned or unplanned events occur

  You can identify the event status of a location by the color of the location icon: blue for normal and orange for exceptional. By clicking a location icon, you can view location details and events in a side pane.

- Shipping Routes

  The following types of shipping routes are displayed on the map with different line format as shown in the map legend. If the legend doesn't appear, click the legend icon to show it.

Route Type	Description
Actual	Drawn to connect the locations with actual events reported. This usually shows the completed part of a shipping route.
Planned	Drawn to connect the locations with planned events. This usually shows the part of a shipping route that hasn't been executed.

  You can click a route to show detailed route information in a side pane.

  ### ⓘ Note

  If a freight document was not executed as planned, the map view shows both the planned route and the actual route.

- Stop/Route Information in Side Pane

When you click a stop or a shipping route in the map, all its relevant planned and unplanned events are displayed as panels in a side pane. The system displays the location and planned date and time for each of these events. You can also view the estimated date and time (if reported) and the actual date and time (if reported). Note that once the actual time is reported, the system does not display the estimated date and time.

You can view the actual events on unplanned stops reported by the carrier though API when you choose the route details.

If a document, such as Proof of Delivery, was uploaded when the carrier manually reported the event, you see an **Attachments** link in the event panel. Click the link to navigate to the attached document.

If an event was reported multiple times, you can click **Details** to view its reporting history. The reporting history shows the date/time, reporter, and sender for each reporting. If a reporting is attached with a document, you can also click **Attachments** to view it.

Reference Business Documents

This section displays the reference document IDs of the freight documents, such as forwarding document ID and visibility provider ID (if any). You can use the forwarding ID to easily find the relevant freight document. The visibility provider ID can be used for troubleshooting in the visibility provider's system.

Attachments

In this section, you can view the attachments uploaded by the carrier or URLs uploaded by the visibility provider for each event reported. These URLs may navigate to documents stored in a third-party document storage service. You can view the following information in this section:

- **Event**
- **Reported By**
- **Event Location**
- **Reported On**
- **Attachment**

Emission Details

In this section, the system displays the emission details in a card format. Note that the system displays this information only when the emission details are reported. The system tracks and reports the carbon emission by tracking the following information:

- **Actual Distance and Actual Means of Transport**

  Displays the following information:

  - Actual distance traversed

    Displays the actual distance traversed from source location to destination location in kilometres or miles

  - Actual means of transport

    Displays the means of transport, for example, truck or vessel

- **Total Carbon Emission for the Shipment**

  Displays the emission for the shipment in either grams, pounds, kilograms, or tonnes. You can select one of the following options to view the emission information:

  - **WTW - Well to Wheel**

    Well to wheels emission is a combination of well-to-tank and tank-to-wheels emissions.