1. Choose the **Docking Location** tab on the left pane.

   The system displays the **Docking Location ID**, **Assigned Yard**, and **Status**.

2. Enter the docking location ID in the search bar on the left pane to search for a specific docking location.

3. Choose a docking location from the results.

   The system displays the detail view of the settings on a right pane.

The detail view consists of a header and other sections.

Header

The header section displays the following information:

- **Docking Location ID**
- **Location ID**
- **Docking Location Icon**

  Displays the docking location icon.

  Also displays a shared sign on this icon when a docking location has enabled sharing with business partners. You can view the sharing details by choosing this icon. The system displays the **Docking Location ID**, **Location ID**, **Shared By**, and **Permissions**.

- **Status**

  Displays one of the following statuses:

  - **Draft**

    This status appears after you create a docking location and choose the **Save** button. You can delete a docking location only when it is in a draft status.

  - **Active**

    This status appears when you activate a draft or an inactive docking location or when you choose the **Save and Activate** button when you create a new docking location.

  - **Inactive**

    This status appears when you deactivate an active docking location by choosing the **Deactivate** button. Note that deactivation may take some time and you may have to refresh your page to get the updated status. You cannot deactivate a docking location that has any reservations or future appointments.

  - **Decommissioned**

    This status appears when you close a docking location by choosing the **Decommission** button. You can only decommission docking locations that are in the inactive status. Once you close a docking location, you cannot activate or perform any actions this location.

  Note that only those docking locations that have their settings activated can be rendered in other apps in the Freight Collaboration option.

Details

The details section displays the following information:

- **Location ID**

  Displays the location ID.

- **Description**

  Displays the docking location description. The system retrieves this information once from the master data of the associated location when the location has been assigned to the docking location.

- **Address**

  Displays the docking location address. The system retrieves this information once from the master data of the associated location when the location has been assigned to the docking location.

  Time Zone

  Displays the time zone of the location. The system retrieves this information once from the master data of the associated location when the location has been assigned to the docking location.

- **Docking Location ID**

- **Cut-Off Time for Appointment Creation**

  Displays whether this setting is disabled or the time at which all loading points in this docking location stop accepting dock appointments from carriers.

- **Appointment Date Change**

  Indicates whether a carrier can change the date of a dock appointment within a range that you specify for each loading point in this docking location.

- **Remarks**

  Displays the additional information about the docking location.

Share Entity

You can share the docking location details with your business partner. Based on the settings you provide here, the business partner can either view or view and edit the docking location details.

This section displays the following information:

- **Created By**

  Displays the details of who created the docking location sharing.

- **Share Entity With**

  Displays the business partners with whom the docking location has been shared with.

- **Permissions**

  Displays whether the business partner can only view or edit the docking location settings.

ℹ Note

You can only share active docking locations with your business partners. That is, when you create a docking location, save, and activate the setting, you can edit the docking location settings and add sharing details.

As a prerequisite, you must establish a relationship with the business partner (shipper) with whom you want to share your docking location. To do so, use the **Invite Business Partners** app and add a new invitee as a shipper. The shipper must operate in the same data center as you. For more information, see Add New Business Partners.

Business Hours

The business hours section displays the business hours of all loading points in the docking location. This section displays the following information:

- **Period**

  Displays the duration for which the entry of business hours is valid.

- **Working Days**

  Displays the working days of the docking location.

- **Working Hours**

  Displays the working hours for the specified working days.

Loading Points

The loading point section displays the following information:

- **Loading Point**
- **Description**
- **Activity Type**

  Displays whether you can perform loading, unloading, or both activities in that loading point.

- **Capacity**

  Displays the number of loading/unloading activities that can be performed concurrently at the loading point.

- **Time Slot Duration**

  Displays the length of a single time slot at the loading point. The duration of activities booked at the loading point must be in multiples of this value.

  When you choose a loading point, the system navigates to the loading point details pane on the right. On this pane, you can view the following additional details of the loading point.

Uploading and Downloading Docking Locations

SAP Business Network Freight Collaboration enables you to simplify the entity management process especially when you have lot of entities to be processed.

You can view, edit, and upload entities using a Microsoft Excel file. This feature enables you to work on multiple entries simultaneously thereby saving a lot of time. You can download and upload the entities in Microsoft Excel format.

In the **Docking Location** tab, in the worklist area on the left, you can view the **Excel** button. When you choose this button, you can select one of the following options:

- **Download**

  You can download all the docking location entities in Microsoft Excel.

- **Upload**

  You can upload the edited Microsoft Excel template containing the docking locations that you want to add.

- **Export Template**

  You can download this Microsoft Excel template file to add the docking locations and upload it in the system.

Download Docking Locations Microsoft Excel

The downloaded docking locations Microsoft Excel file contains the following worksheets:

- Docking Locations

  This worksheet contains all the information in the docking location **Details** tab in the **Manage Entities** app. You can view the following columns:

  - Docking Location Reference

    As the docking location information has been split across different worksheets in this Microsoft Excel file, the system has created this reference ID in the Microsoft Excel file. When you switch to another worksheet, you can use this reference ID to logically map the relevant data.

  - Docking Location ID
  - Location ID
  - Appointment Date Change
  - Cut-Off Time for Appointment Creation
  - Cut-Off Days
  - Cut-Off Time
  - Time Zone

  Note

  For docking location entities in draft status, you can edit all the above fields.

  For docking location entities in active and inactive statuses, you can edit the **Appointment Date Change**, **Cut-Off Time for Appointment Creation**, **Cut-Off Days**, and **Cut-Off Time** fields. All the other fields are non-editable similar to the edit option in docking locations in the **Manage Entities** app.

- **Business Working Hours**

  This worksheet contains all the information in the **Business Hours** tab in the **Manage Entities** app. You can view the following columns:

  - Docking location reference
  - Time period reference
  - Start date
  - End date
  - Working days
  - Start time
  - End time

  Note that you can edit all the fields in this worksheet similar to the edit option in docking locations in the **Manage Entities** app.

- **Associations**

  This worksheet contains the associations between the docking location and the loading point. You can view the **Docking Location Reference** and the associated **Loading Point Reference** in this worksheet.

- Loading Point Master

This worksheet contains all the information in the **Loading Points** tab in the **Manage Entities** app. You can view the following columns:

- Loading point reference
- Loading point ID
- Description
- Activity type
- Capacity
- Time slot (duration)
- Status

Note that all the fields in this worksheet are non-editable similar to the edit option in docking locations in the **Manage Entities** app.

Upload Docking Locations Microsoft Excel

To upload the docking locations in a Microsoft Excel file, perform the following:

1. You can use the docking locations file that you previously downloaded using the **Download** option to edit the existing data.

   Alternatively, you can download the template by choosing **Docking Location** > **Excel** > **Export Template** option to add new docking locations. This template contains the same worksheets and columns similar to the downloaded docking locations Microsoft Excel file. However, it does not contain any data.

   Note that you can only use either the template or the downloaded file to upload into the system.

2. Upload the Excel file by choosing **Docking Location** > **Excel** > **Upload**.

   Upload entities dialog box appears.

3. Select the edited file that you want to upload from your computer and choose **Proceed**.

   The system displays the confirmation message indicating the number of docking location entities that will be uploaded. It will also display the error log if some of the entities are in error state. You can download the error log to investigate the issue.

4. Choose **Confirm** to upload the entities.

   Displays whether the entities are uploaded. If they are uploaded, you can view them in the **Docking Location** tab in the app.

ℹ Note

There are a few columns that are hidden in the worksheets. These columns contain technical information. You cannot edit these columns

Adding of **Enable Sharing** option is currently not available in the Microsoft Excel file.

You cannot edit the status of the docking location in the Microsoft Excel file. You can only change the status in the **Manage Entities** app.

You can only upload Microsoft Excel files with a maximum of 2500 entries.

Defining Gate Settings

Gate settings define operational parameters such as location, time zone, and business hours for managing gate activities efficiently.

To define the settings for a gate, proceed as follows:

1. Choose the **Gate** tab on the left pane.
2. Choose the **Add Gate** button.

   The create gate pane appears on the right.
3. Define settings for the following sections:
   - **Details**
   - **Business Hours**
4. Choose **Save** to save the gate settings as a draft. Choose **Save and Activate** to activate the gate settings.

ℹ Note

The following fields cannot be changed any longer after the gate was activated:

- Gate ID
- Location ID
- Description
- Address
- Time Zone
- Direction

Details

Enter the following information in the details section:

- **Location ID**

  Select a location ID. You maintain location master data in the **Manage Locations** app.
- **Time Zone**

  Enter a time zone.
- **Gate ID**

  Specify a gate ID.
- **Arrival Lead Time**

  Select the minimum time before which the driver must arrive at the gate. For example, if you select 1:30 minutes here, the vehicle must arrive at the gate 1 hour and 30 minutes prior to the scheduled appointment time.

  Contact Name

  Specify the name of a contact person responsible for this gate.
- **Phone Number**

  Specify the phone number of the contact person responsible for this gate.
- **Direction**

  Specify whether this gate supports inbound, outbound, or both inbound and outbound activities.

- **Assignment with Yards**

  If you enable this setting, the gate can be associated with multiple yards in the same time zone. If you disable this setting, the gate can be associated with only one yard in the same time zone. When you enable this setting, the system displays the following:

  - **Assigned Yards**

    You can select the yards with which you want to share the gate.

- **Remarks**

  Enter the additional information about the gate.

Business Hours

Choose the add icon in this section to add an entry of business hours.

> **Note**
> You can add only one entry of business hours for a gate.

Enter the following information:

- **Period**

  Specify the duration for which the entry of business hours is valid.

- **Working Days**

  Specify the working days of the gate.

- **Working Hours**

  Specify the working hours for the specified working days.

  To add another entry of validity period, choose the add icon. You can create up to 10 entries per validity period.

Viewing a Gate

Shows the gate settings, such as location, time zone, and business hours.

To view the gate settings, proceed as follows:

1. Choose the **Gate** tab on the left pane.
2. Enter the gate ID in the search bar on the left pane to search for a specific gate.
3. Choose a gate from the results.

   The system displays the detail view of the settings on a right pane.

   The detail view consists of a header and other sections.

Header

The header section displays the following information:

- **Gate ID**

- Location ID
- Shared

  Displays Shared whether this gate has enabled sharing with multiple yards
- Gate Icon

  Displays the gate icon.

  Also displays a shared sign on this icon when a gate has enabled sharing with business partners. You can view the sharing details by choosing this icon. The system displays the Gate ID, Location ID, Shared By, and Permissions.
- Status

  Displays one of the following statuses:

  - Draft

    This status appears after you create a gate and choose the Save button. You can delete a gate only when it is in a draft status.
  - Active

    This status appears when you activate a draft or an inactive gate or when you choose the Save and Activate button while creating a new gate.
  - Inactive

    This status appears when you deactivate a gate by choosing the Deactivate button. Note that deactivation may take some time and you may have to refresh your page to get the updated status. You cannot deactivate a gate that is part of a gate logbook.
  - Decommissioned

    This status appears when you close a gate by choosing the Decommission button. You can only decommission gates that are in the inactive status. Once you decommission a gate, you cannot activate or perform any actions.

Details

The Details section displays the following information:

- Location ID
- Description

  Displays the location description. The system retrieves this information once from the master data of the associated location when the location has been assigned to the gate.
- Address

  Displays the location address. The system retrieves this information once from the master data of the associated location when the location has been assigned to the gate.
- Time Zone

  Displays the time zone of the location. The system retrieves this information once from the master data of the associated location when the location has been assigned to the gate.
- Gate ID
- Arrival Lead Time

Displays the minimum time before which the driver must arrive at the gate. For example, if you enter 30 minutes here, the vehicle must arrive at the gate 30 minutes prior to the scheduled arrival time.

- **Contact Person**

  Displays the name and phone number of the contact person responsible for this gate in a card format.

- **Direction**

  Displays whether this gate supports inbound, outbound, or both inbound and outbound activities.

- **Assignment with Yards**

  Displays whether the gate is associated with multiple yards or a single yard. If this setting is enabled, you can view the shared yards.

  - **Assigned Yards**

    Displays the yards with which the gate has been shared.

- **Remarks**

  Displays additional information about the gate.

Share Entity

You can share the gate details with your business partner. Based on the settings you provide here, the business partner can either view or edit the gate details.

This section displays the following information:

- **Created By**

  Displays the details of who created the gate sharing.

- **Share Entity With**

  Displays the business partners with whom the gate has been shared with.

- **Permissions**

  Displays whether the business partner can only view or edit the gate settings.

ℹ Note

You can only share active gates with your business partners. That is, when you create a gate, save, and activate the setting, you can edit the gate settings and add sharing details.

As a prerequisite, you must establish a relationship with the business partner (shipper) with whom you want to share your gate. To do so, use the **Invite Business Partners** app and add a new invitee as a shipper. The shipper must operate in the same data center as you. For more information, see Add New Business Partners.

Business Hours

This section displays the business hours of the gate. This section displays the following information:

- **Period**

  Displays the duration for which the entry of business hours is valid.

- **Working Days**

Displays the working days of the gate.

- **Working Hours**

  Displays the working hours for the specified working days.

Uploading and Downloading Gates

SAP Business Network Freight Collaboration enables you to simplify the entity management process especially when you have lot of entities to be processed.

You can view, edit, and upload entities using a Microsoft Excel file. This feature enables you to work on multiple entries simultaneously thereby saving a lot of time. You can download and upload the entities in Microsoft Excel format.

In the **Gate** tab, in the worklist area on the left, you can view the **Excel** button. When you choose this button, you can select one of the following options:

- **Download**

  You can download all the gate entities in Microsoft Excel.

- **Upload**

  You can upload the edited Microsoft Excel template containing the gates that you want to add.

- **Export Template**

  You can download this Microsoft Excel template file to add the gates and upload it in the system.

Download Gates Microsoft Excel

The downloaded gates Microsoft Excel file contains the following worksheets:

- **Gate**

  This worksheet contains all the information in the gate **Details** tab in the **Manage Entities** app. You can view the following columns:

  - Gate reference

    As the gate information has been split across different worksheets in this Microsoft Excel file, the system has created this reference ID in the Microsoft Excel file. When you switch to another worksheet, you can use this reference ID to logically map the relevant data.

  - Gate ID
  - Location ID
  - Contact person
  - Phone number
  - Direction
  - Arrival lead time
  - Time Zone

ℹ Note

For gate entities in draft status, you can edit all the above fields.