The **All** worklist displays all freight orders that you have not yet responded to and responded to. For each freight order, the following information is displayed:

- Ordering party and freight order
- Freight order status
- Remaining time / Freight quotation

  Displays the remaining time provided by the ordering party for you to respond in days or minutes. You can view the remaining time as **Expired** if the remaining time is over. Note that this information is populated only in direct tendering scenario.

  For more information, see frequently asked questions for Freight Orders for Confirmation App.
- Freight order ID
- Arrival and departure address

  Displays the country code, street, and postal code.
- Arrival and departure date and time
- Arrival and departure location
- Arrival and departure state
- Reference documents

  When you choose the number of reference documents on the worklist, you can view the type and ID for each reference document.
- Dangerous goods
- Document category

  Displays whether the document is a **Shipment** from SAP ECC or a **Freight Order** or a **Consignment Order** from SAP Transportation Management (SAP TM) or TM on SAP S/4HANA system.
- Mode of transport
- Price
- Requested loading start and end date time
- Acceptable loading start and end date time
- Requested loading duration

  Displays the duration between the requested loading start date time and requested loading end date time
- Normalized quantity and additional normalized quantity
- Scenario
- Shipping type
- Stops

  When you choose the number of stops on the worklist, you can view the stop number and location for each stop.
- Total gross volume
- Total gross weight

- Total quantity
- Transport means description
- Transport means type
- Vendor ID
- My response
- Departure State

  The state as specified in the departure address.
- Arrival State

  The state as specified in the arrival address.

The freight orders are only displayed if the arrival date and time has not yet been reached.

New

The **New** worklist displays the freight orders that you have not yet responded to or those that have been updated. The **New** worklist displays the same information as the **All** worklist except for the column that displays your response.

> **Note**
> If you rejected a freight order and the shipper sends a cancellation, it is displayed in the **All** worklist with status **Cancellation confirmed**.

Responded To (Open)

The **Responded To (Open)** worklist displays all freight orders that you've already responded to. The **Responded To (Open)** worklist displays the same information as the **All** worklist.

You can select one or more freight orders and choose to either **Confirm** or **Reject** from the worklist page.

You can choose to export the worklist into a spreadsheet by choosing the **Export to Spreadsheet** icon on the top right corner of the worklist table.

> **Note**
> The freight orders are only displayed if the arrival date and time has not yet been reached.
>
> You can view the unit of measure along with total gross weight, total gross volume, and total quantity. However, when you download the freight orders in a Microsoft Excel sheet, the system still displays the unit of measures for these attributes in separate columns to enable easy sorting.
>
> Some of the fields that are not relevant for documents with the document category as **Shipment Not Relevant**.

Detail View (Freight Orders for Confirmation)

The detail view of a freight order for confirmation consists of a header and several sections.

> **Note**

Some of the fields and tabs that are not relevant for a shipment document are not displayed in freight orders with the document category as **Shipment**.

Header

The **Header** section displays important data about the freight order as well as data related to the response you can send to your ordering party.

The following fields may be of particular interest for you:

- General details

  Displays the freight order ID, document category, ordering party, and consignee party. Document category displays whether the document is a freight order or a shipment. When you choose the ordering party or consignee party, you can view the address and contact details.

- Price (**Negotiable** or **Non-negotiable**)

  Whether the price is negotiable or not depends on the ordering party's decision.

- Submitted price

- Remaining time (**Confirm Automatically: Yes/No**)

  If it says **Confirm Automatically: Yes**, the network will automatically confirm the freight order for you unless you reject it before the remaining time runs out.

  The remaining time is not a mandatory field. Depending on the ordering party's setup, you may not be restricted by a dedicated response due date time.

- Your latest response (**Confirmed**, **Confirmed with Change**, **Rejected**, **Confirmed Automatically**)

- Contact details of the ordering party

- Freight order status (**New**, **New (updated)**, **Updated**, **Confirmed**, **Confirmed with change**, **Automatically confirmed**, **Rejected Canceled**, **Cancellation confirmed**)

Information

The information tab contains the **General** section and the **Reference Documents** section. You can view the following details in these sections:

- You can view a message that highlights the number of notes in the notes section and you can also navigate to the notes section when you choose **View All**.

- General

  Displays the following information:

  - **Freight Order ID**
  - **Total Distance**
  - **Total Duration**
  - **Response Due Date And Time**
  - **Number Of Loading Stops**
  - **Number Of Unloading Stops**

- Mode Of Transport
- Total Gross Weight
- Total Gross Volume
- Total Gross Quantity
- Normalized Quantity
- Additional Normalized Quantity

Note

- In the Assign Codes app, if you do not maintain the mapping between Code in External System and LBN Code for the values in the below table, then the system does a default mapping to the respective value.

Mode of Transport

SAP Transportation Management System	SAP Business Network for Logistics System
03 - Ocean	01 - Ocean
01 - Road	03 - Road
05 - Air	04 - Air

- Departure location

  Displays the date and time of departure, address and additional address of departure location.

- Arrival location

  Displays the date and time of arrival, address and additional address of arrival location.

- Transport requirements

  Displays whether you have opted to view the details of dangerous goods and the temperature requirements.

  ### Note

  If the ordering party has entered dangerous goods information in their SAP Transportation Management (TM) system, this information is transferred to SAP Business Network for Logistics. To view this information, in the Information section, choose Yes under Dangerous Goods, which opens a window containing details about the item type, relevant regulations, and more detailed information such as storage instructions, temperature control, and emergency temperature. You can choose to display the dangerous goods information in any language that the ordering party has specified previously in the TM system.

- Active vehicle resource

  Displays the transport means description, transport means type, vehicle code, vehicle type code, and vehicle resource ID of the vehicle.

- Terms and conditions

  Displays the incoterm and incoterm location.

  Note that you can view the incoterm location details that the ordering party has added in the Manage Locations app. If the ordering party has not added this information, you can view the text specified for incoterm location in the ordering party's external transportation system.

- Administrative data

  Displays the date and time the freight order was received, details of the last responded person and time.

- Reference documents section

  Displays the document type and document ID of the reference documents. You can add a reference document by choosing the add icon. Enter the document type and document ID of the reference document and choose **Send Update** to send an update to the ordering party.

  Note that you can add reference documents with the document types such as **Global Location Number**, **Motor Carrier Number**, **United States Department of Transportation**, and so on for executing carriers so that the ordering party can use this information for tracking purposes.

  You can also download the reference document details in a spreadsheet. You can view the following details in this document:

  - **Document ID**
  - **Document Type Code**
  - **Document Type Description**
  - **Created On (UTC)**
  - **Created By**

Cargo and Service Items

This section displays the following data about the cargo items involved:

Service Items

In this sub-section, the system displays the number of document services and cargo services. When you choose the number, you can view the additional details of all the document services and cargo services in a dialog box.

Cargo

In this sub-section, the system displays the cargo item ID as the combination of **Item ID** with the parent hierarchy separated by colon as the prefix in freight documents with the document category as **Shipment**.

- **Cargo Item / Description**

  Displays the description of the cargo item.

- **Type**

  Displays whether the cargo item is a package, product, or a container.

  Note that if the cargo item is a container, the system displays this field as **Type/ID**. You can enter the container ID in the field next to container cargo type.

- **Logistical Details**

  Displays the quantity, gross weight, gross volume, and dimensions.

  Also displays the normalized quantity.

- **Equipment Details**

  Displays the equipment type and equipment group.

- **Special Requirements**

  Displays the following:

  - **Dangerous Goods**

    If the ordering party has provided dangerous goods information, you can view this information from the **Cargo** section by choosing **Yes** in the **Dangerous Goods** column. This opens a window containing details about the item type, relevant regulations, and more detailed information such as storage instructions, control temperature, and emergency temperature.

  - **Temperature Requirements**

- **Reference Document**

  You can view the following:

  - Customer purchase order details
  - Document ID and document type of the SAP Enterprise Resource Planning (SAP ERP) reference documents such as inbound delivery, outbound delivery, sales order, and purchase order document associated in the SAP Transportation Management system.

- **Other Details**

  Displays the following:

  - Over-Dimensional

    Displays whether the cargo item is over-dimensional

  - Non-Stackable
  - High Value
  - Seal Details

    When you choose this button, you can view the seal details in a dialog box. You can view the seal numbers and seal parties. Note that this button appears only in container line items.

  - Cargo Services

    This field is visible when cargo services are available for a cargo item. Choosing it displays the detailed information.

ℹ Note

- You can view the details of all cargo item types such as container, package, product, and service. You can navigate through the entire cargo item hierarchy. For example, from a container to the packages, package to the products or services and so on to view the respective details.
- The ordering party can implement a business add-in (BAdI) to display only the main cargo items.

  Any notes sent by the ordering party with text type `LBNMI` will be discarded as it is a technical text type used to display main cargo items.

  You can view the aggregated dangerous goods information for the filtered items at the main cargo item level.

Stops and Stage Details

When you select a cargo item and choose **View Stage and Stop Details**, you can view the stop and stage details for the cargo item. In the **Stop Details** tab, for each stop within the stop sequence, the address of the ordering party is displayed.

You can toggle between the **Loading** and **Unloading** buttons to view the information specific to the activity. The **Loading** tab displays the following details:

- Loading start date and time
- Loading end date and time
- Acceptable start date and time
- Acceptable end date and time
- Cargo items to be loaded

The **Unloading** tab displays the following details:

- Unloading start date and time
- Unloading end date and time
- Acceptable start date and time
- Acceptable end date and time
- Cargo items to be unloaded

Charges

The **Charges** section displays the following information:

- Charge description

  Displays the charge type details for each stage in each freight document. Charge types are the classification of charges for which you charge the ordering party.

- Charge type (Transportation System)

  Classification of charge line that indicates the type of charges such base rate, surcharge, or discount, as specified in the ordering party's SAP Transportation Management system.

- Rate amount/unit

  Displays the flat rate amount or rate amount per unit, for example, USD 20 per 1 kg.

- Quantity

  Displays the total quantity relevant for calculating the final amount.

- Final amount

  Displays the final amount that has been derived from the rate amount, quantity, and calculation method.

When you select a charge, you can view the following additional details specific for the selected charge:

- Transportation charges

  You can view the charge details such as line number, charge type, calculation methods, and payment terms.

  - Line number
  - Charge description

Displays the classification of charges for which you charge the ordering party. These are the transportation mode-specific codes that are predefined by SAP Business Network for Logistics.

- Calculation method

  Displays the logic with which the system calculates the charges.

- Payment terms

  Displays the conditions of payment you agreed with your ordering party with respect to goods supplied or services provided.

- Logistical reference

  Displays the item or stage information for a charge line (for container, package, product, or stage) from which the system obtains the logistical data.

- Calculation basis

  Displays the actual base or factor with which the system calculated the charges. You can view the calculation basis for rates belonging to a rate table.

- Exchange rates

  Displays the exchange rate information that is used as the basis for currency conversion.

- Notes

  Displays the notes specified for the charge line.

Tour

The **Tour** section displays the stop sequence. For each stop, you can view the following information:

- Stop number
- Location

  You can click the link to view both the main and additional address of the location.

- Arrival and departure date and time
- Activity
- Distance to next location
- Time to next location

Contacts

If provided by the ordering party, the **Contacts** section displays the company name of the ordering party along with the phone number and the email address of the contact person. This section also displays the contact details for each individual stop (stop number and location).

Notes

The **Notes** section displays the comments previously left by the ordering party and yourself, as well as enabling you to add new notes. Note: When you add a new note, it is only sent when you confirm or reject the freight order.

Note

- Notes are intended to provide additional information related to the business document or business process. You're recommended to avoid entering sensitive personal data.
- Any notes sent by the ordering party with text type `LBNMI` will be discarded as it is a technical text type used to display main cargo items.

Attachments

The **Attachments** section displays the attachments the ordering party has sent you, as well as letting you upload your own attachments.

Drivers and Resource Details

The **Drivers and Resource Details** section enables you to provide the names of the drivers who will drive the vehicle as well as provide the vehicle license plate.

You can specify the following details:

- **Driver Details**: Name and mobile numbers of the driver and additional driver
- **Resource Details**: Truck license plate and country or region of registration, truck ID, and trailer ID

Note

- The mobile number, truck ID, and trailer ID details are sent to the ordering party to their SAP Transportation Management system.
- The driver mobile number and the truck ID details that you enter here are used for tracking purposes.
- This section is not available in consignment orders.

Confirming a Freight Order

If you agree with the price and the dates given by the ordering party, you can confirm a freight order without proposing a change.

Context

You can confirm a freight order that fulfills the following criteria:

- The **Freight Order Status** is **New**, **New (Updated)**, **Confirmed**, **Confirmed with Change**, and **Confirmed Automatically** even if the arrival date is in the past.
- The **Freight Order Status** is **Rejected**, **Canceled** or **Cancellation Confirmed** along with a future arrival date.

You can also confirm a freight order that you previously rejected or confirmed with a change, as long as the freight order has not been closed by the ordering party.

Procedure

1. Open the **Freight Orders for Confirmation** app.
2. Within a worklist (**New**, **Responded To**, or **All**), select one or more open freight orders. To confirm a single freight order, you can also use the detail view.
3. Choose **Confirm**.

   After confirming the freight order, the **Confirm** button changes to **Send Update** (unless there is still remaining time available). Clicking **Send Update** enables you to send information to the ordering party that you were unable to provide when confirming the freight order.

Confirming a Freight Order with a Change

You can confirm a freight order with a change.

Context

If the ordering party wants to receive proposals for alternative prices to those which they specified in the freight order, then you can make a proposal by confirming the freight order with a change. And, as long as the remaining time has not run out and the freight order has not been closed by the ordering party, you can confirm a freight order and make a price proposal for freight orders that you previously rejected or confirmed.

ℹ Note

The ordering party can maintain a setting in their transportation management system to either enable or disable you from modifying the price proposal currency. Based on this setting, for the direct tendering scenario, when you confirm a freight order with change, the system either enables you to modify the price proposal currency or does not allow you to do so. You can view these details in the information icon next to the price proposal currency, in the dialog box, which appears when you choose the **Confirm with Change** button in the freight order.

Note that when you change the price proposal currency, the system automatically updates the settlement currency to be the same as the updated price proposal currency.

Procedure

1. Open the **Freight Orders for Confirmation** app.
2. Within a worklist (**New**, **Responded To**, or **All**), look for the open freight order for which you want to enter changes. Alternatively, you can also open the detail view of the freight order.
3. Choose **Confirm with Change**.
4. Enter your price proposal.
5. Choose **Confirm with Change**.

Rejecting a Freight Order

You can reject a freight order if you are unable to or do not want to take on the transportation.

Context

As long as the remaining time to respond hasn't run out and the freight order has not been closed by the ordering party, you can reject a freight order, even if you previously confirmed it.

You can reject a freight order as long as the arrival date and time has not passed.