To enable inbound connections for **Multi-Cloud**, proceed as follows:

Procedure

1. In the **System Connections** app, on the **Configuration Settings** view, activate the **Enable Inbound Connections** toggle. For new users, the toggle is disabled by default.
2. Select the integration platform. You can choose between **Multi-Cloud** and **Neo (deprecated)**. Neo is selected by default.
3. (For **Multi-Cloud** only) Select the Provider APIs to which you want to have access, and save. You can update the Provider API selection later.
4. View the service credentials (client ID, client secret, authentication URL, and host URL). You can copy them and enter them when you create the OAuth 2.0 authentication details. For more information, see: Specifying the Authentication Details and Base URLs for Your System's Endpoints.

   For more information, refer to the instructions in the provider API specification of SAP Business Network Global Track and Trace, under https://api.sap.com/package/LbnGlobalTrackAndTrace?section=Overview.

   To enable inbound connections for **Neo**, proceed as in step 1. By default, inbound communication is authenticated with OAuth 2.0. To acquire the OAuth 2.0 credentials for **Neo (deprecated)**, create an incident with component SBN-LBN-INT.

Manage Alternate IDs (Data Contributor)

You can maintain alternate identifiers of your other accounts in the network. These identifiers shall be used in specific integration scenarios or in specific transaction flows in the network.

Additionally, the LBN ID of your tenant can be seen above the **Alternate IDs** table as a read-only field.

SAP Business Network for Logistics supports the following alternate identifiers (alternate IDs):

- DUNS ID (Data Universal Numbering System ID)
- SCAC (Standard Carrier Alpha Code)
- Registration Number
- USDOT (US Department of Transportation)
- MC Number (Motor Carrier Number)
- Others
- GLN (Global Location Number)
- Technical User

To create your own alternate IDs, proceed as follows:

1. Choose **Manage Alternate IDs**.
2. Select an alternate ID type from the dropdown menu and type in the required value.
3. Choose **OK**.

You can also delete or change existing entries.

Define User Settings

The **Define User Settings** app allows you to define defaults that best suit the way you work. The settings that you make in the app serve as the default settings in various other apps for .SAP Business Network Global Track and Trace

Distance

In this section, you can define the default unit of measurement for distance. The system uses this setting in other apps in your area.

Notification Subscriptions

In this section, you can subscribe to notifications for various scenarios and specify the email address and preferred language for receiving the notifications. Note that you cannot subscribe to a scenario without maintaining an email address.

When you subscribe to notifications for a scenario, the system can send email notifications based on the settings you make in the **Manage Notification Settings** app.

For more information on managing notification settings, see Manage Notification Settings.

Manage Invitations

Note

This app is available for data contributors only.

The **Manage Invitations** app allows you to manage all the invitations you receive from potential business partners to connect with their business network.

The app consists of the following areas:

- Filter bar

  You can filter the invitations based on one or more of the filter options, such as inviter's company name, email, city, country/region, that appear in the header area.

- Worklists by status

  The invitations are categorized based on the invitation statuses: **New**, **Accepted**, and **Rejected**.

Worklist (Manage Invitations)

There are different ways to work on the invitations and to set filters. To restrict the number of invitations displayed, you can use the filter bar in the header and the preconfigured worklists (**New**, **Accepted**, **Rejected**) based on the status of the invitation.

Filter Bar

With the filter bar, you can do the following:

- Specify filters to narrow down the worklists and search for invitations.
- Add or remove the filters displayed on the filter bar by choosing **Adapt Filters**.
- Save the current filter settings as a view and apply it later.

After you specified filters (and pressed Enter) and/or adapted filter display, the current view name shown in the upper-left corner displays a * sign, indicating the view has been changed. Save the view by either of the following:

- Click the view name to open the **My Views** box and choose **Save** or **Save As**.
- In the **Adapt Filters** dialog box, choose **Save**.

Next time when you want to apply the view, just select the view name in the **My Views** box.

> **Note**
> The default **Standard** view cannot be changed.

Worklists

New

The **New** worklist displays all invitations that you have not yet responded to. This worklist displays the following details for each invitation:

- Invitation Number
- Inviter
- Inviter LBN Network ID
- Invitation From
- Phone number
- Email
- City
- Country/Region
- Address
- Accept and reject options

Accepted

The **Accepted** worklist displays all the invitations that you have accepted. This worklist displays the following details for each invitation:

- Invitation Number
- Inviter
- Inviter LBN Network ID
- Invitation From
- Phone number
- Email
- City
- Country/Region
- Address

- Administration information such as Accepted On and Accepted By

Rejected

The **Rejected** worklist displays all the invitations that you have rejected. This worklist displays the following details for each invitation:

- Invitation Number
- Inviter
- Inviter LBN Network ID
- Invitation From
- Phone number
- Email
- City
- Country/Region
- Address
- Administration information such as Rejected On and Rejected By

Note

Using the *Settings* icon on each worklist, you can control the number of columns displayed in the **New**, **Accepted**, and **Rejected** worklists.

Viewing an Invitation

Context

To view an invitation, perform the following:

Procedure

1. Launch the **Manage Invitations** app.
2. You can view all the new invitations in the **New** worklist.

   (Optional) You can retrieve a specific invitation or a set of invitations using the various search filter options such as the inviter's company name, email, city, country/region, that appear on the header area.

   The system also categorizes the invitations based on various attributes and displays them in the following tabs:

   - **New**: Displays all new invitations from potential business partners.
   - **Accepted**: Displays invitations that you have accepted.
   - **Rejected**: Displays invitations that you have rejected.

Accepting or Rejecting an Invitation

Context

You can accept or reject the invitations from potential business partners to connect with their business network. When rejecting, you can indicate a rejection reason to the inviter.

If you accept an invitation, you can connect with the inviter's business network and the system notifies the inviter of the same. If you reject an invitation, you cannot connect with the inviter's business network and the system notifies the inviter of the same.

To accept or reject an invitation, perform the following:

Procedure

1. Launch the **Manage Invitations** app. You can view all the new invitations in the **New** worklist. You can directly accept or reject the invitations in this worklist.
2. Alternatively, you can search for and retrieve a specific invitation using search filter options in the header. Once you retrieve the invitation, you can respond to the invitation by choosing the **Accept** or **Reject** button.

Results

Once you accept or reject an invitation, you can view the details of the invitation in the **Accepted** or **Rejected** worklist as appropriate. You cannot view this invitation anymore in the **New** worklist.

Settings on Invitations

You can specify the visibility of your company profile and how you process connection requests in the app. To do this, click **Settings on Invitations** on the upper-right concern then specify the followings:

- **Automatically accept connection requests (invitations)**

  Determines whether you want the app to automatically accept connection requests from potential business patterns.

  Default value: No

Manage Notification Settings

You can use this app to schedule reminder notifications for some of the business processes for which you may need an alert.

The system sends you notifications via emails.

The **Manage Notification Settings** app consists of the following areas:

- List of scenarios

  This area displays the scenarios for which you can configure alerts.

- Filter

  You can use this filter to filter the scenarios. When you select a scenario from this drop-down menu, the system displays only that specific scenario.

- Configuration details

  The system displays the following in this area:

- Configurations

  The system displays notification types and the settings that you can configure for each type.

  On-event notification refers to the email notification that you receive at the time when a target event happens, for example, when you receive an invitation from a shipper.

  Post-event notifications refer to the notifications you receive after the target event happens, for example, after you have received the invitation.

- Subscribers

  The system displays the list of users who have subscribed to notifications for the current scenario. The subscription is made in the **Define User Settings** app.

Scenarios

As a data contributor, you can schedule email notifications for the following scenario:

Scenario Group	Scenario	For receiving email notifications when, before or after ...
Business Operations	Integration Error V2	The system now sends an email notification to you when an integration error occurs.

ℹ Note

To enable email notifications for the above scenarios, you need to activate the settings in this app and subscribe to notifications for the scenarios in the **Define User Settings** app.

Related Information

Define User Settings

Configure Notification Settings

Prerequisites

To enable reminder notifications, make sure you also maintain an email address and subscribe to the notification(s) you need in the **Define User Settings** app. For more information, see Define User Settings

Context

You can configure the following types of notifications in the **Manage Notification Settings** app, where applicable.

On-Event Notification

On-event notification refers to the email notification that you receive at the time when a target event happens, for example, when you receive an invitation from a shipper. You can activate or deactivate on-event notification by setting the activation toggle to **Yes** or **No**, respectively.

Pre-Event Notifications

Pre-event notifications refer to the notifications you receive before the target event happens, for example, before dock appointment booking cut-off. You can schedule pre-event notifications by adding notification periods and specifying notification frequency within each period, as described below:

- Notification period: The period within which email notifications will be sent in a specified frequency.

  You only specify the start of the period, for example, **30 days before the event**, which means the notification period starts from 30 days before the event till the start of the next period or the event time.

- Frequency: The frequency to receive notifications within the specified period. For example, setting the frequency to **every 5 days** means within the specified period, you'll receive an email notification every 5 days.

Example

The schedule shown below

Notification Period	Frequency	Activated for User
60 days	Every 10 days	Yes
30 days	Every 5 days	Yes
15 days	Every 3 days	Yes

specifies the following schedule:

- Within the period from 60 days before the event to 30 days before the event, receive a notification every 10 days.
- Within the period from 30 days before the event to 15 days before the event, receive a notification every 5 days.
- Within the period from 15 days before the event till the event time, receive a notification every 3 days.

In the same example, if you deactivate the "30 days" period, as shown below:

Notification Period	Frequency	Activated for User
60 days	Every 10 days	Yes
30 days	Every 5 days	**No**
15 days	Every 3 days	Yes

Then the "30 days" period is ignored and the schedule changes to:

- Within the period from 60 days before the event to 15 days before the event, receive a notification every 10 days.
- Within the period from 15 days before the event till the event time, receive a notification every 3 days.

Post-Event Notifications

Post-event notifications refer to the notifications you receive after the target event happens, for example, after you have received the invitation. You can schedule post-event notifications by adding notification periods and specifying notification frequency within each period, as described below:

- Notification period: The period within which email notifications will be sent in a specified frequency.

You only specify the end of the period, for example, **30 days after the event**, which means the notification period starts from the end of the previous period or the event time, to 30 days after the event.

- Frequency: The frequency to receive notifications within the specified period. For example, setting the frequency to **every 5 days** means within the specified period, you'll receive an email notification every 5 days.

Example

The schedule shown below

Notification Period	Frequency	Activated for User
15 days	Every 3 days	Yes
30 days	Every 5 days	Yes
60 days	Every 10 days	Yes

specifies the following schedule:

- Within the period from the event time to 15 days after the event, receive a notification every 3 days.
- Within the period from 15 days after the event to 30 days after the event, receive a notification every 5 days.
- Within the period from 30 days after the event to 60 days after the event, receive a notification every 10 days.

Note that for the invitations scenario, the notifications stop as soon as the invitation is accepted or rejected.

In the same example, if you deactivate the "30 days" period, as shown below:

Notification Period	Frequency	Activated for User
15 days	Every 3 days	Yes
30 days	Every 5 days	**No**
60 days	Every 10 days	Yes

Then the "30 days" period is ignored and the schedule changes to:

- Within the period from the event time to 15 days after the event, receive a notification every 3 days.
- Within the period from 15 days after the event to 60 days after the event, receive a notification every 10 days.

Procedure

1. Launch the **Manage Notification Settings** app.
2. In the scenario list, select the scenario for which you want to set notifications.
3. To activate on-event notification, for **On-Event Notification**, set the toggle to **Yes**. To deactivate, set it to **No**.
4. To configure pre-event or post-event notifications, do the following:
    a. Expand the **Pre-Event Notifications** or **Post-Event Notifications** area.
    b. To add a notification period, choose the **Add** button. Then in the **Add Notification Period** dialog box, specify the start (pre-event) or end (post-event) of the period and the frequency, and choose **Save**. You can add multiple periods according to your needs.

c. To edit or delete a notification period, choose the **Edit** or **Delete** button. To deactivate a period, set **Activated for User** to **No**.

Manage Freight Execution

The **Manage Freight Execution** app enables you to view the execution of the freight documents by tracking planned and unplanned events that occurred during freight execution. You can also report various planned and unplanned events.

Also, you can perform the following in this new app:

- **Planned milestone events**

  You can view the milestones planned by the ordering party

- **Planned and unplanned events**

  You can report various planned and unplanned events.

- **Estimate**

  You can report an estimate for any planned event.

- **Delay**

  You can report delays at both the document-level and at an event-level.

- **Proof of pick-up and delivery**

  You can submit proof of pick-up and proof of delivery with attachments.

- **Additional events**

  You can report additional events for the supported event types at any stop.

- **Event history**

  You can view all the events reported by you and all other business partners. You can also view the event history for a specific planned event.

- **Attachments**

  You can view all the attachments specific to the freight execution in the **Attachments** tab.

This app contains the track relevant freight documents irrespective of whether the documents are relevant for confirmation or not. This app also contains documents that are ready for tracking from the SAP Business Network Global Track and Trace.

In this app, you can view the events that you reported manually and the events reported by other business partners. The manually reported data and the events reported by the APIs are synchronized to the SAP Transportation Management (SAP TM) or SAP S/4 HANA system.

Note that you can report events for a freight order even when you have not reconfirmed a freight order that has been updated by the ordering party.

This app consists of a main view and a detailed view.

When you open the app, the main view is displayed. It consists of two screen areas:

- Filter bar

Using the filter bar in the header, you can filter the freight documents by one of the following criteria to restrict the number of freight documents displayed:

- **Freight Document**
- **Freight Document Type**
- **Departure Location**
- **Arrival Location**
- **Departure Date**
- **Arrival Date**
- **Created On**
- **Reference Documents**
- **Mode of Transport**

  Category of transportation, for example, road, ocean, air, and so on.

- **Reporting Status**

  Displays the reporting status based on the documents that are ready for reporting. For more information on current status, see Freight Execution Statuses.

- **Execution Status**

  Displays whether the freight is **Ready for Execution** or **In Transit**. For more information, see Freight Execution Statuses.

- **Current Status**

  Displays the current status of execution based on the latest planned event reported. You can view whether the execution is as planned, early, on time, or late. For more information on current status, see Freight Execution Statuses.

- **Estimated Status**

  Displays the estimated status of execution based on the latest estimate received for a planned event. You can view whether the execution is as running early, running on time, or running late. Note that this is relevant before the planned event has been reported. For more information on estimated status, see Freight Execution Statuses.

- **Arrival Country**

  The last arrival location of a freight document.

- **Carrier**
- **Container**
- **Dangerous Goods**
- **Departure Country**
- **IMO Number**

  The International Maritime Organization (IMO) number is a unique identifier assigned to propelled, seagoing vessels of 100 gross tons and above. It consists of the three letters "IMO" followed by unique seven-digit numbers.

- **License Plate Number**
- **Proof of Delivery Status**