




UNIVERSITY OF THE EAST
CALOOCAN CITY
College of Engineering
Department of Computer Studies and Systems

GRE
Packet Tracer Activities

Name: AGUSTIN, LJ
Student Number: 20231132788
Subject and Section: CIT3201 - (IT1F)

Activity No.	Score
ACT3	98%

Activity 03



SITE 1

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#h SITE1
SITE1(config)#int g0/2
SITE1(config-if)#ip add 192.168.2.1 255.255.255.0
SITE1(config-if)#no sh
SITE1(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2,
changed state to up
SITE1(config-if)#ex
SITE1(config)#int g0/0
SITE1(config-if)#ip add 192.168.3.1 255.255.255.0
SITE1(config-if)#no sh
SITE1(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
SITE1(config-if)#ex
SITE1(config)#int g0/1
SITE1(config-if)#ip add 192.168.4.1 255.255.255.0
SITE1(config-if)#no sh
SITE1(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
SITE1(config-if)#ex
SITE1(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0,
changed state to up
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1,
changed state to up
SITE1(config)#int tunnel10
SITE1(config-if)#
%LINK-5-CHANGED: Interface Tunnel10, changed state to up
SITE1(config-if)#ip add 10.0.1.1 255.255.255.0
SITE1(config-if)#tunnel source g0/1
SITE1(config-if)#tunnel dest 10.0.1.2
SITE1(config-if)#tunnel dest 192.168.12.1
SITE1(config-if)#no sh
SITE1(config-if)#ex
SITE1(config)#router eigrp 31
SITE1(config-router)#network 192.168.2.0 0.0.0.255
SITE1(config-router)#network 192.168.3.0 0.0.0.255
SITE1(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 31: Neighbor 192.168.3.2
(GigabitEthernet0/0) is up: new adjacency
SITE1(config-router)#network 192.168.4.0 0.0.0.255
SITE1(config-router)#network 10.0.1.0 0.0.0.255
SITE1(config-router)#no auto-summary
SITE1(config-router)#ex
```

SITE2

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#h SITE2
SITE2(config)#int g0/2
SITE2(config-if)#ip add 192.168.2.1 255.255.255.0
SITE2(config-if)#no sh
SITE2(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2,
changed state to up
SITE2(config-if)#ex
SITE2(config)#int g0/1
SITE2(config-if)#ip add 192.168.5.2 255.255.255.0
SITE2(config-if)#no sh
SITE2(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
SITE2(config-if)#ex
SITE2(config)#int g0/0
SITE2(config-if)#ip add 192.168.3.2 255.255.255.0
SITE2(config-if)#no sh
SITE2(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0,
changed state to up
SITE2(config-if)#ex
SITE2(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1,
changed state to up
```

```

SITE2(config)#int tunnel20
SITE2(config-if)#
%LINK-5-CHANGED: Interface Tunnel20, changed state to up
SITE2(config-if)#ip add 10.0.2.1 255.255.255.0
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1,
changed state to down
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1,
changed state to up
SITE2(config-if)#tunnel source g0/1
SITE2(config-if)#tunnel dest 192.168.9.1
SITE2(config-if)#no sh
SITE2(config-if)#ip route 192.168.9.0 255.255.255.252 10.0.2.2
SITE2(config)#int tunnel20
SITE2(config-if)#no ip route 192.168.9.0 255.255.255.252 10.0.2.2
SITE2(config)#ip route 192.168.9.0 255.255.255.0 10.0.2.2
SITE2(config)#router eigrp 31
SITE2(config-router)#network 192.168.2.0 0.0.0.255
SITE2(config-router)#network 192.168.3.0 0.0.0.255
SITE2(config-router)#network 192.168.5.0 0.0.0.255
SITE2(config-router)#network 10.0.2.0 0.0.0.255
SITE2(config-router)#no auto-summary
SITE2(config-router)#ex
SITE2(config)#

```

SP1

```

Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#h SP1
SP1(config)#int g0/0
SP1(config-if)#ip add 192.168.5.1 255.255.255.0
SP1(config-if)#no sh
SP1(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0,
changed state to up
SP1(config-if)#ex
SP1(config)#int g0/1
SP1(config-if)#ip add 192.168.6.2 255.255.255.0
SP1(config-if)#no sh
SP1(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
SP1(config-if)#ex
SP1(config)#int g0/2
SP1(config-if)#ip add 192.168.7.1 255.255.255.0
SP1(config-if)#no sh
SP1(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up
SP1(config-if)#ex
SP1(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2,
changed state to up

```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1,
changed state to up
SP1 con0 is now available
Press RETURN to get started.
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0,
changed state to down
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0,
changed state to up
Enter configuration commands, one per line. End with CNTL/Z.
SP1(config)#router eigrp 31
SP1(config-router)#network 192.168.5.0 0.0.0.255
SP1(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 31: Neighbor 192.168.5.2
(GigabitEthernet0/0) is up: new adjacency
SP1(config-router)#network 192.168.6.0 0.0.0.255
SP1(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 31: Neighbor 192.168.6.1
(GigabitEthernet0/1) is up: new adjacency
SP1(config-router)#network 192.168.7.0 0.0.0.255
SP1(config-router)#no auto-summary
SP1(config-router)#ex
SP1(config)#
```

SP2

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#h SP2
SP2(config)#int g0/0
SP2(config-if)#ip add 192.168.4.2 255.255.255.0
SP2(config-if)#no sh
SP2(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0,
changed state to up
SP2(config-if)#ex
SP2(config)#int g0/1
SP2(config-if)#ip add 192.168.8.2 255.255.255.0
SP2(config-if)#no sh
SP2(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
SP2(config-if)#ex
SP2(config)#int g0/2
SP2(config-if)#ip add 192.168.7.2 255.255.255.0
SP2(config-if)#no sh
SP2(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2,
changed state to up
SP2(config-if)#ex
SP2(config)#
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1,
changed state to up
SP2 con0 is now available
Press RETURN to get started.
SP2(config)#router eigrp 31
SP2(config-router)#network 192.168.4.0 0.0.0.255
SP2(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 31: Neighbor 192.168.4.1
(GigabitEthernet0/0) is up: new adjacency
SP2(config-router)#network 192.168.7.0 0.0.0.255
SP2(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 31: Neighbor 192.168.7.1
(GigabitEthernet0/2) is up: new adjacency
SP2(config-router)#network 192.168.8.0 0.0.0.255
SP2(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 31: Neighbor 192.168.8.1
(GigabitEthernet0/1) is up: new adjacency
SP2(config-router)#no auto-summary
SP2(config-router)#ex
```

R1

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#h R1
R1(config)#int g0/0
R1(config-if)#ip add 192.168.6.1 255.255.255.0
R1(config-if)#no sh
R1(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0,
changed state to up
R1(config-if)#ex
R1(config)#int g0/1
R1(config-if)#ip add 192.168.9.2 255.255.255.0
R1(config-if)#no sh
R1(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
R1(config-if)#ex
R1(config)#int g0/2
R1(config-if)#ip add 192.168.10.2 255.255.255.0
R1(config-if)#no sh
R1(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up
R1(config-if)#ex
R1(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1,
changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2,
changed state to up
R1(config)#router eigrp 31
R1(config-router)#network 192.168.6.0 0.0.0.255
```

```
R1(config-router)#network 192.168.9.0 0.0.0.255
R1(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 31: Neighbor 192.168.9.1
(GigabitEthernet0/1) is up: new adjacency
R1(config-router)#network 192.168.10.0 0.0.0.255
R1(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 31: Neighbor 192.168.10.1
(GigabitEthernet0/2) is up: new adjacency
R1(config-router)#no auto-summary
R1(config-router)#ex
```

HQa

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#h HQa
HQa(config)#int g0/0
HQa(config-if)#ip add 192.168.10.1 255.255.255.0
HQa(config-if)#no sh
HQa(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0,
changed state to up
HQa(config-if)#ex
HQa(config)#int g0/1
HQa(config-if)#ip add 192.168.14.1 255.255.255.0
HQa(config-if)#no sh
HQa(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1,
changed state to up
HQa(config-if)#ex
HQa(config)#
HQa con0 is now available
Press RETURN to get started.
HQa>en
HQa#conf t
Enter configuration commands, one per line. End with CNTL/Z.
HQa(config)#int tunnel30
HQa(config-if)#
%LINK-5-CHANGED: Interface Tunnel30, changed state to up
HQa(config-if)#ip add 10.0.3.1 255.255.255.0
HQa(config-if)#tunnel source g0/0
HQa(config-if)#tunnel des 192.168.12.1
HQa(config-if)#tunnel des 10.0.3.2
HQa(config-if)#tunnel des 192.168.12.1
HQa(config-if)#no sh
HQa(config-if)#ex
HQa(config)#ip route 192.168.12.0 255.255.255.0 10.0.3.2
HQa(config)#router eigrp 31
HQa(config-router)#network 192.168.10.0 0.0.0.255
HQa(config-router)#network 192.168.14.0 0.0.0.255
```

```
HQa(config-router)#network 10.0.3.0 0.0.0.255
HQa(config-router)#no auto-summary
HQa(config-router)#ex
```

HQy

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#h HQy
HQy(config)#int g0/0
HQy(config-if)#ip add 192.168.9.1 255.255.255.0
HQy(config-if)#no sh
HQy(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0,
changed state to up
HQy(config-if)#ex
HQy(config)#int g0/1
HQy(config-if)#ip add 192.168.13.1 255.255.255.0
HQy(config-if)#no sh
HQy(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1,
changed state to up
HQy(config-if)#ex
HQy(config)#
HQy(config)#int tunnel20
HQy(config-if)#
%LINK-5-CHANGED: Interface Tunnel20, changed state to up
HQy(config-if)#ip add 10.0.2.2 255.255.255.0
HQy(config-if)#tunnel source g0/0
HQy(config-if)#tunnel des 192.168.5.2
HQy(config-if)#no sh
HQy(config-if)#ex
HQy(config)#ip route 192.168.5.0 255.255.255.0 10.0.2.1
HQy(config)#router eigrp 31
HQy(config-router)#network 192.168.9.0 0.0.0.255
HQy(config-router)#network 192.168.13.0 0.0.0.255
HQy(config-router)#network 10.0.2.0 0.0.0.255
HQy(config-router)#no auto-summary
HQy(config-router)#ex
```

R2

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#h R2
R2(config)#int g0/0
R2(config-if)#ip add 192.168.8.1 255.255.255.0
R2(config-if)#no sh
R2(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
```



```

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0,
changed state to up
R2(config-if)#ex
R2(config)#int g0/1
R2(config-if)#ip add 192.168.12.2 255.255.255.0
R2(config-if)#no sh
R2(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
R2(config-if)#ex
R2(config)#int g0/2
R2(config-if)#ip add 192.168.11.2 255.255.255.0
R2(config-if)#no sh
R2(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/2, changed state to up
R2(config-if)#ex
R2(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/2,
changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1,
changed state to up
R2(config)#router eigrp 31
R2(config-router)#network 192.168.8.0 0.0.0.255
R2(config-router)#network 192.168.11.0 0.0.0.255
R2(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 31: Neighbor 192.168.11.1
(GigabitEthernet0/2) is up: new adjacency
R2(config-router)#network 192.168.12.0 0.0.0.255
R2(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 31: Neighbor 192.168.12.1
(GigabitEthernet0/1) is up: new adjacency
R2(config-router)#no auto-summary
R2(config-router)#ex

```

HQb

```

Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#h HQb
HQb(config)#int 0/0
^
% Invalid input detected at '^' marker.

HQb(config)#int g0/0
HQb(config-if)#ip add 192.168.11.1 255.255.255.0
HQb(config-if)#no sh
HQb(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0,
changed state to up
HQb(config-if)#ex
HQb(config)#int g0/1
HQb(config-if)#ip add 192.168.15.1 255.255.255.0

```

```
HQb(config-if)#no sh
HQb(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1,
changed state to up
HQb(config-if)#ex
HQb(config)#
HQb con0 is now available
Press RETURN to get started.
HQb>en
HQb#conf t
Enter configuration commands, one per line. End with CNTL/Z.
HQb(config)#int tunnel30
HQb(config-if)#
%LINK-5-CHANGED: Interface Tunnel30, changed state to up
HQb(config-if)#ip add 10.0.3.2 255.255.255.0
HQb(config-if)#tunnel source g0/0
HQb(config-if)#tunnel des 192.168.10.1
HQb(config-if)#no sh
HQb(config-if)#ex
HQb(config)#
HQb(config)#router eigrp 31
HQb(config-router)#network 192.168.11.0 0.0.0.255
HQb(config-router)#network 192.168.15.0 0.0.0.255
HQb(config-router)#network 10.0.3.0 0.0.0.255
HQb(config-router)#no auto-summary
HQb(config-router)#ex
HQb(config)#ip route 192.168.10.0 255.255.255.0 10.0.3.1
HQb(config)#
```

HQz

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#h HQz
HQz(config)#int g0/0
HQz(config-if)#ip add 192.168.12.1 255.255.255.0
HQz(config-if)#no sh
HQz(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0,
changed state to up
HQz(config-if)#ex
HQz(config)#int g0/1
HQz(config-if)#ip add 192.168.16.1 255.255.255.0
HQz(config-if)#no sh
HQz(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1,
changed state to up
HQz(config-if)#ex
HQz(config)#
```

```
HQz(config)#int tunnel10
HQz(config-if)#
%LINK-5-CHANGED: Interface Tunnel10, changed state to up
HQz(config-if)#ip add 10.0.1.2 255.255.255.0
HQz(config-if)#tunnel source g0/0
HQz(config-if)#tunnel dest 192.168.4.1
HQz(config-if)#no sh
HQz(config-if)#ex
HQz(config)#ip route 192.168.4.0 255.255.255.0 10.0.1.1
HQz(config)#router eigrp 31
HQz(config-router)#network 192.168.12.0 0.0.0.255
HQz(config-router)#network 192.168.16.0 0.0.0.255
HQz(config-router)#network 10.0.1.0 0.0.0.255
HQz(config-router)#no auto-summary
HQz(config-router)#ex
HQz(config)#
```