

The SATM System

	Welcome to Rock Solid Federal Credit Union Please insert your ATM card						
Printed receipt	1	2	3	Card slot			
	4	5	6	Enter			
	7	8	9	Clear			
		0		Cancel			
Cash dispenser				Deposit slot			

Screen 1

Welcome
please insert your
ATM card

Screen 2

Please enter your PIN

Screen 3

Your PIN is incorrect.
Please try again.

Screen 4

Invalid ATM card. It will
be retained.

Screen 5

Select transaction:
balance >
deposit >
withdrawal >

Screen 6

Balance is
\$dddd.dd

Screen 7

Enter amount.
Withdrawals must
be multiples of \$10

Screen 8

Insufficient Funds!
Please enter a new
amount

Screen 9

Machine can only
dispense \$10 notes

Screen 10

Temporarily unable to
process withdrawals.
Another transaction?

Screen 11

Your balance is being
updated. Please take
cash from dispenser.

Screen 12

Temporarily unable to
process deposits.
Another transaction?

Screen 13

Please insert deposit
into deposit slot.

Screen 14

Your new balance is
being printed. Another
transaction?

Screen 15

Please take your
receipt and ATM card.
Thank you.

The SATM system

- The SATM system communicates with bank customers via the 15 screens.
- SATM customers can select any of three transaction types: deposits, withdrawals, and balance inquiries.
- When a bank customer arrives at an SATM station, screen 1 is displayed.
- The bank customer accesses the SATM system with a plastic card encoded with a personal account number (PAN).
- If the customer's PAN matches the information in the customer account file, the system presents screen 2 to the customer. If the customer's PAN is not found, screen 4 is displayed, and the card is kept.
- At screen 2, the customer is prompted to enter his or her personal identification number (PIN).
- If the PIN is correct the system displays screen 5; otherwise, screen 3 is displayed. The customer has three chances to get the PIN correct; after three failures, screen 4 is displayed, and the card is kept.

- On entry to screen 5, the customer selects the desired transaction from the options shown on screen. If balance is requested, screen 14 is then displayed.
- If a problem occurs with the deposit envelope slot, the system displays screen 12, else screen 7 is displayed.
- Once the deposit amount has been entered, the system displays screen 13, accepts the deposit envelope, and processes the deposit. The system then displays screen 14.
- If a withdrawal is requested, but it is jammed, screen 10 is displayed; otherwise, screen 7 is displayed so the customer can enter the withdrawal amount.
- The system checks the customer balance and if the funds in the account are insufficient, screen 8 is displayed. If the account balance is sufficient, screen 11 is displayed and the money is dispensed.
- The balance is printed on the transaction receipt as it is for a balance request transaction. After the cash has been removed, the system displays screen 14.

The currency converter

Currency converter

US dollar amount

Equivalent in ...

☐ Brazil

☐ Canada

☐ European community

☐ Japan

Compute

Clear

Quit

- The application converts US dollars to any of four currencies: Brazilian reals, Canadian dollars, European Union euros, and Japanese yen.
- Currency selection is governed by the radio buttons (option buttons), which are mutually exclusive.
- When a country is selected, the system responds by completing the label; for example, “Equivalent in ...” becomes “Equivalent in Canadian dollars” if the Canada button is clicked.
- The user inputs an amount in US dollars. Once both tasks are accomplished, the user can click on the Compute button, the Clear button, or the Quit button.
- Clicking on the Compute button results in the conversion of the US dollar amount to the equivalent amount in the selected currency.
- Clicking on the Clear button resets the currency selection.
- Clicking on the Quit button ends the application.