
Configure hostname, enable passwords, username and password, clock and date



```
Type help or '?' for a list of available commands.
ciscoasa>
ciscoasa>
ciscoasa>
ciscoasa>
ciscoasa>
ciscoasa>
ciscoasa>
ciscoasa>enable
Password:
ciscoasa#conf terminal
ciscoasa(config) #hostname PERIMETER-FW
PERIMETER-FW (config) #enable password Gtech12
PERIMETER-FW (config) #
PERIMETER-FW(config) #username Gtech password Gtech123
PERIMETER-FW (config) #
PERIMETER-FW (config) #
PERIMETER-FW(config) #clock set ?
configure mode commands/options:
  hh:mm:ss Current Time
PERIMETER-FW(config) #clock set clock set 17:51:30 20 July 2024
% Invalid input detected at '^' marker.
PERIMETER-FW (config) #
PERIMETER-FW (config) #
PERIMETER-FW(config) #clock set 17:51:30 20 July 2025
PERIMETER-FW (config) #
PERIMETER-FW (config) #
PERIMETER-FW (config) #int gigl/1
PERIMETER-FW(config-if) #int gigl/1
PERIMETER-FW (config-if) #no shut
PERIMETER-FW (config-if) #
· Invalla Impas acocosca as
PERIMETER-FW (config) #
PERIMETER-FW (config) #
```

```
PERIMETER-FW (config) #clock set 17:51:30 20 July 2025
PERIMETER-FW (config) #
PERIMETER-FW (config) #
PERIMETER-FW (config) #int gig1/1
PERIMETER-FW(config-if) #int gigl/1
PERIMETER-FW (config-if) #no shut
PERIMETER-FW(config-if) #ip add 192.168.100.1 255.255.255.0
PERIMETER-FW (config-if) #
PERIMETER-FW(config-if) #nameif INSIDE
INFO: Security level for "INSIDE" set to 0 by default.
PERIMETER-FW (config-if) #
PERIMETER-FW (config-if) #
PERIMETER-FW (config-if) #security-level 100
PERIMETER-FW (config-if) #exit
PERIMETER-FW (config) #
```

Configure IP addresses, names, and security level to interfaces

```
PERIMETER-FW (config-if) #exit
PERIMETER-FW (config) #
PERIMETER-FW (config) #
PERIMETER-FW (config) #
PERIMETER-FW (config) #
PERIMETER-FW(config) #int gig1/3
PERIMETER-FW (config-if) #no shutdown
PERIMETER-FW (config-if) #
PERIMETER-FW (config-if) #
PERIMETER-FW(config-if) #ip add 10.10.10.1 255.255.255.240
PERIMETER-FW (config-if) #
PERIMETER-FW (config-if) #
PERIMETER-FW(config-if) #nameif DMZ
INFO: Security level for "DMZ" set to 0 by default.
PERIMETER-FW (config-if) #
PERIMETER-FW (config-if) #
PERIMETER-FW(config-if) #security-level 70
PERIMETER-FW (config-if) #exit
PERIMETER-FW (config) #
PERIMETER-FW (config) #
PERIMETER-FW (config) #
PERIMETER-FW (confid) #
PERIMETER-FW(config)#
PERIMETER-FW (config) #
PERIMETER-FW (config) #int gig1/2
PERIMETER-FW (config-if) #no shutdown
PERIMETER-FW (config-if) #
PERIMETER-FW (config-if) #
PERIMETER-FW(config-if) #ip add 20.20.20.1 255.255.255.0
PERIMETER-FW (config-if) #
PERIMETER-FW (config-if) #
PERIMETER-FW (config-if) #
PERIMETER-FW(config-if) #nameif OUTSIDE
INFO: Security level for "OUTSIDE" set to 0 by default.
PERIMETER-FW (config-if) #
PERIMETER-FW (config-if) #
PERIMETER-FW(config-if) #security-level 0
PERIMETER-FW (config-if) #exit
PERIMETER-FW (config) #
PERIMETER-FW (config) #
PERIMETER-FW (config) #
PERIMETER-FW (config) #
```

```
PERIMETER-FW(config) #wr mem
Building configuration...
Cryptochecksum: 5d732c45 5633182c 4a246702 68c9483e
1256 bytes copied in 1.972 secs (636 bytes/sec)
[OK]
PERIMETER-FW (config) #write memory
Building configuration...
Cryptochecksum: 5d732c45 5633182c 4a246702 68c9483e
1256 bytes copied in 2.332 secs (538 bytes/sec)
[OK]
PERIMETER-FW (config) #
PERIMETER-FW (config) #
PERIMETER-FW (config) #
PERIMETER-FW (config) #sh start
: Saved
: Written by enable_15 at 18:07:13 UTC Jul 20 2025
: Call-home enabled from prompt by enable 15 at 18:07:13 UTC Jul 20 2025
ASA Version 9.6(1)
hostname PERIMETER-FW
enable password qJVZegIIqtedDq2d encrypted
names
interface GigabitEthernet1/1
nameif INSIDE
security-level 100
ip address 192.168.100.1 255.255.255.0
interface GigabitEthernet1/2
nameif OUTSIDE
security-level 0
ip address 20.20.20.1 255.255.255.0
interface GigabitEthernet1/3
nameif DMZ
security-level 70
<---> More --->
```

