rvu@rvu-OptiPlex-SFF-7020: ~/Desktop/Manu.R

GNU nano 7.2 a7.sh

```
#!/bin/bash
display_memory_usage() {
    echo "Current Memory Usage:"
    free -h
    echo ""
}
monitor_memory_usage() {
    echo "Monitoring memory usage in real-time. Press [CTRL+C] to stop."
    top -o %MEM
}
while true
do
    echo "1. Display current memory usage"
    echo "2. Monitor memory usage in real-time"
    echo "3. Exit"
    read -p "Select an option (1-3): " option
    case $option in
        1)
            display_memory_usage
            ;;
        2)
            monitor_memory_usage
            ;;
        3)
            echo "Exiting the memory monitor. Goodbye!"
            exit 0
            ;;
        *)
            echo "Invalid option. Please select 1-3."
            ;;
    esac
    echo ""
done
```

rvu@rvu-OptiPlex-SFF-7020: ~/Desktop/Manu.R

```
rvu@rvu-OptiPlex-SFF-7020:~/Desktop/Manu.R$ nano a7.sh
rvu@rvu-OptiPlex-SFF-7020:~/Desktop/Manu.R$ chmod +x a7.sh
rvu@rvu-OptiPlex-SFF-7020:~/Desktop/Manu.R$ ./a7.sh
1. Display current memory usage
2. Monitor memory usage in real-time
3. Exit
Select an option (1-3): 1
Current Memory Usage:
              total        used        free      shared  buff/cache   available
Mem:           15Gi       2.6Gi        10Gi       595Mi       2.6Gi        12Gi
Swap:         4.0Gi          0B       4.0Gi


1. Display current memory usage
2. Monitor memory usage in real-time
3. Exit
Select an option (1-3): 2
Monitoring memory usage in real-time. Press [CTRL+C] to stop.



top - 14:27:19 up 21 min,  1 user,  load average: 0.45, 0.54, 0.38
Tasks: 375 total,   1 running, 374 sleeping,   0 stopped,   0 zombie
%Cpu(s):  0.2 us,  0.1 sy,  0.0 ni, 99.7 id,  0.0 wa,  0.0 hi,  0.0 si,  0.0 st
MiB Mem :  15675.7 total,  10938.1 free,   2634.8 used,   2685.6 buff/cache
MiB Swap:   4096.0 total,   4096.0 free,      0.0 used.  13041.0 avail Mem

    PID USER      PR  NI    VIRT    RES    SHR S  %CPU  %MEM     TIME+ COMMAND
   4839 rvu       20   0   11.5g 630404 287936 S   0.0   3.9   3:22.50 firefox
   6053 rvu       20   0 2960460 370892 119204 S   0.7   2.3   0:29.18 Isolated Web Co
   5596 rvu       20   0 2976520 327040 122060 S   0.0   2.0   0:41.00 Isolated Web Co
   2506 rvu       20   0 4744864 313784 132912 S   2.6   2.0   2:01.79 gnome-shell
   6006 rvu       20   0 2701808 187440 103904 S   0.0   1.2   0:03.01 Isolated Web Co
   5030 rvu       20   0 2701028 180216 102964 S   0.0   1.1   0:11.40 Privileged Cont
   5235 rvu       20   0 2639024 115072  79692 S   0.0   0.7   0:00.87 WebExtensions
   5904 rvu       20   0 2735796 101512  79744 S   0.0   0.6   0:00.91 Isolated Web Co
   7096 rvu       20   0 2596836  77896  61648 S   0.0   0.5   0:00.79 Web Content
```

```
1. Display current memory usage
2. Monitor memory usage in real-time
3. Exit
Select an option (1-3): 3
Exiting the memory monitor. Goodbye!
rvu@rvu-OptiPlex-SFF-7020:~/Desktop/Manu.R$ nano a7.sh
rvu@rvu-OptiPlex-SFF-7020:~/Desktop/Manu.R$
```