OS LAB COMPONENTS

Name: Ninada S A
31.3.26
USN: 1RUA25BCA0075

8.Environment Variables in Unix Shell:

Code-

```bash
#!/bin/bash
display_env() {
echo "Current Environment Variables:"
printenv
}

set_env() {
read -p "Enter variable name: " name
read -p "Enter variable value: " value

export $name=$value
echo "Variable $name set successfully."
}

show_env() {
echo "Environment variables using env command:"
env
}

while true
do
echo "----- Environment Variable Manager -----"
echo "1. Display variables (printenv)"
echo "2. Set new variable"

echo "3. Display variables (env)"
echo "4. Exit"

read -p "Enter choice: " ch

case $ch in
1) display_env ;;
2) set_env ;;
3) show_env ;;
4) exit ;;
*) echo "Invalid choice" ;;
esac
done
```

Output-

```
(base) rvu@rvu-OptiPlex-SFF-7020:~/0075$ nano envi.sh
(base) rvu@rvu-OptiPlex-SFF-7020:~/0075$ chmod +x envi.sh
(base) rvu@rvu-OptiPlex-SFF-7020:~/0075$ ./envi.sh
----- Environment Variable Manager -----
1. Display variables (printenv)
2. Set new variable
3. Display variables (env)
4. Exit
Enter choice: 1
Current Environment Variables:
SHELL=/bin/bash
SESSION_MANAGER=local/rvu-OptiPlex-SFF-7020:@/tmp/.ICE-unix/2344,unix/rvu-OptiPlex-SFF-7020:/tmp/.ICE-unix/2344
QT_ACCESSIBILITY=1
COLORTERM=truecolor
XDG_CONFIG_DIRS=/etc/xdg/xdg-ubuntu:/etc/xdg
XDG_MENU_PREFIX=gnome-
GNOME_DESKTOP_SESSION_ID=this-is-deprecated
CONDA_EXE=/home/rvu/anaconda3/bin/conda
_CE_M=
GNOME_SHELL_SESSION_MODE=ubuntu
SSH_AUTH_SOCK=/run/user/1000/keyring/ssh
MEMORY_PRESSURE_WRITE=c29tZSAyMDAwMDAgMjAwMDAwMAA=
XMODIFIERS=@im=ibus
DESKTOP_SESSION=ubuntu
GTK_MODULES=gail:atk-bridge
PWD=/home/rvu/0075
GSETTINGS_SCHEMA_DIR=/home/rvu/anaconda3/share/glib-2.0/schemas
XDG_SESSION_DESKTOP=ubuntu
LOGNAME=rvu
XDG_SESSION_TYPE=wayland
CONDA_PREFIX=/home/rvu/anaconda3
SYSTEMD_EXEC_PID=2383
GSETTINGS_SCHEMA_DIR_CONDA_BACKUP=
XAUTHORITY=/run/user/1000/.mutter-Xwaylandauth.QEC2M3
HOME=/home/rvu
```

```
Enter choice: 2
Enter variable name: Ninada
Enter variable value: 0075
Variable Ninada set successfully.
----- Environment Variable Manager -----
1. Display variables (printenv)
2. Set new variable
3. Display variables (env)
4. Exit
Enter choice: 4
(base) rvu@rvu-OptiPlex-SFF-7020:~/0075$ nano envi.sh
(base) rvu@rvu-OptiPlex-SFF-7020:~/0075$
```