Skaldic Saga Log Mod

Server-Side Installation & Configuration Guide

This guide details how to install and configure the server-side **Skaldic Saga Log** mod. Because this plugin runs purely on the server runtime engine, connecting clients do not need to install the mod to receive the poetry broadcasts in their text logs.

Phase 1: Preparing the Server with BepInEx

Before executing customized assemblies, your server infrastructure must harbor the BepInEx framework.

- **Download Framework:** Navigate to Thunderstore.io and download the latest stable release of **BepInExPack Valheim**.
- **Extract Files:** Extract the contents of the zip file archive locally on your system.
- **Deploy to Root:** Move the internal files directly into your Valheim server's root installation folder (where *valheim_server.exe* or *valheim_server.x86_64* resides).
- **Initialize Core:** Launch your server framework completely once. This boots up the initialization scripts and automatically generates the empty **BepInEx/plugins/** subdirectories.

Phase 2: Deploying the Mod Plugin (.dll)

- **Locate Library Binary:** Grab your freshly compiled **SkaldicSaga.dll** file from your Visual Studio environment build directory (typically found under *bin/Release/*).
- **Target Plugins Folder:** Access your server file ecosystem and enter the **BepInEx/plugins/** pathway.
- **Transfer Binary:** Upload or drop your *SkaldicSaga.dll* asset file directly into that plugins directory.
- **Reboot Runtime:** Restart your server console completely. Look at the initialization logs to confirm success: *[Info : BepInEx] Loading [SkaldicSagaLog 1.0.0]*.

Server Navigation Frameworks

Server Architecture	Access Mechanism & Key Directory Navigation Path
Dedicated Hosted Server (G-Portal, Nitrado, PingPerfect, etc.)	1. Log in to your hosting platform's web dashboard web console. 2. Locate your **FTP Credentials** (Host IP, Port, User, Password). 3. Connect using an FTP utility like **FileZilla**. 4. Open the remote folder root and navigate to: `/BepInEx/plugins/`
Self-Hosted Local Server (Spare Desktop PC / Batch Loop)	1. Access the local hardware asset executing your server loop. 2. Open Windows File Explorer. 3. Navigate to the absolute installation workspace where your game world executes: `C:\YourServerFolder\BepInEx\plugins\`

Phase 3: Configuration & Anti-Spam Mitigation

To shield your multiplayer gameplay from excessive scrolling text logs, configure your cooldown metrics inside the auto-generated config token file:

File Path Location: `BepInEx/config/com.user.skaldicsaga.cfg`

```
[General]
## Minimum minutes between saga broadcasts to prevent chat spam.
# Setting type: Int32
# Default value: 15
CooldownMinutes = 15
```

• **Note:** Elevate this index integer value on heavily populated community servers to preserve the clean presentation of standard cooperative tactical communications.

This document serves structural modding reference deployments for Valheim systems. Ensure proper backup states before altering live multiplayer cloud files.