Documentation Pro Pricing **Teams**



Sign Up

Sign In

Search packages

Search

run-rs

0.7.7 • Public • Published a year ago



Code (Beta)

7 Dependencies

6 Dependents

54 Versions

run-rs

Zero-config MongoDB runner. Starts a replica set with no non-Node dependencies, not even MongoDB.



Usage

To install:

npm install run-rs -g

With run-rs, starting a 3 node replica set running MongoDB 3.6 is a one-liner.

run-rs

To use a different version, use the -v flag. For example, this will start a 3 node replica set using MongoDB 4.0.0.

run-rs -v 4.0.0

On linux, for 4.2.0 version, by default download ubuntu1604, change with command

run-rs -l ubuntu1804

Clearing the Database

Run-rs clears the database every time it starts by default. To override this behavior, use the --keep (-k) flag.

run-rs --keep

OS Support

Run-rs supports Linux, OSX, and Windows 10 (via git bash or powershell).

Shell Option

Use the --shell flag to start a MongoDB shell connected to your replica set once the replica set is running.

```
$ run-rs --shell
Purging database...
Running '/home/node/lib/node_modules/run-rs/3.6.5/mongod'
Starting replica set...
Started replica set on "mongodb://localhost:27017,localhost:27018,localhost:27019"
Connecting shell /home/node/lib/node_modules/run-rs/3.6.5/mongo
rs:PRIMARY>
```

Notes on Connecting

Use replicaSet=rs in your connection string.

For Windows Users: Do NOT use localhost or 127.0.0.1 for the host name in your connection string, use *computer name* instead. See example connection string below:

```
mongodb://sk-zm-los-bdb:27017,sk-zm-los-bdb:27018,sk-zm-los-bdb:27019/dbname?replicaSet=rs
```

where sk-zm-los-bdb is the hostname or the name of your computer, dbname is the name of your database, and rs is the name of your replica set.

Reusing a Pre-installed MongoDB Version

By default, run-rs will download whatever version of MongoDB you've specified. If you already have MongoDB installed, you can use the --mongod option:

```
run-rs --mongod
```

The above command will just run whatever mongod is on your PATH. If you want to run a specific mongod server, you can do this:

```
run-rs --mongod /home/user/path/to/mongod
```

Specify the data directory

By default, run-rs will store data files in a directory named 'data'. To specify a dbPath for run-rs to use as a data directory, use the -- dbpath option.

```
run-rs --dbpath /path/to/data/directory
```

IP Binding

Use the --host option to ensure that run-rs allows MongoDB to listen for connections on configured IP addresses or hostnames other than localhost and 127.0.0.1. See examples below:

```
run-rs --host 198.51.100.1
```

Note: Before you bind to other ip addresses, consider **enabling access control** and other security measures listed in **Security Checklist** to prevent unauthorized access.

Ports

By default, run-rs will start MongoDB servers on ports 27017, 27018, and 27019. You can override this default using the --portStart option. For example, the below command will start MongoDB servers on ports 27000, 27001, and 27002.

run-rs --portStart 27000

Running in Production

Do **not** use run-rs for running your production database. Run-rs is designed for local development and testing, and is not intended for production use. If you want to run MongoDB in production and don't want to manage a replica set yourself, use **MongoDB Atlas**.

Keywords

mongodb replica replica set runner

Install

> npm i run-rs

Repository

• github.com/vkarpov15/run-rs

Homepage

5,715

𝕝 github.com/vkarpov15/run-rs#readme

★ Weekly Downloads

Version License

0.7.7 Apache 2.0

Unpacked Size Total Files

48.4 kB

Issues Pull Requests

23

Last publish

a year ago

Collaborators



>_Try on RunKit





Support

Help

Advisories

Status

Contact npm

Company

About

Blog

Press

Terms & Policies

Policies

Terms of Use

Code of Conduct

Privacy