
Server-PT
Server0
PC-PT
Attacker PC
1941
Router0
2960-24TT
Switch0
PC-PT
Internal PC

Simulation Panel

Event List

Vis.	Time(sec)	Last Device	At Device	Type
	0.963	--	Switch0	STP
	0.964	Switch0	Server0	STP
	0.964	Switch0	Router0	STP
	0.964	Switch0	Internal PC	STP
	2.965	--	Switch0	STP
Visible	2.966	Switch0	Server0	STP
Visible	2.966	Switch0	Router0	STP
Visible	2.966	Switch0	Internal PC	STP

Router0

Physical Config CLI Attributes

```
            cisco Systems, Inc.
            170 West Tasman Drive
            San Jose, California 95134-1706

Cisco IOS Software, C1900 Software (C1900-UNIVERSALK9-M), Version 15.1(4)M4, RELEASE SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2012 by Cisco Systems, Inc.
Compiled Thurs 5-Jan-12 15:41 by pt_team
Image text-base: 0x2100F918, data-base: 0x24729040

This product contains cryptographic features and is subject to United
States and local country laws governing import, export, transfer and
use. Delivery of Cisco cryptographic products does not imply
third-party authority to import, export, distribute or use encryption.
Importers, exporters, distributors and users are responsible for
compliance with U.S. and local country laws. By using this product you
agree to comply with applicable laws and regulations. If you are unable
to comply with U.S. and local laws, return this product immediately.

A summary of U.S. laws governing Cisco cryptographic products may be found at:
http://www.cisco.com/wwl/export/crypto/tool/stqrg.html

If you require further assistance please contact us by sending email to
export@cisco.com.

Cisco CISCO1941/K9 (revision 1.0) with 491520K/32768K bytes of memory.
Processor board ID FTX152400KS
2 Gigabit Ethernet interfaces
DRAM configuration is 64 bits wide with parity disabled.
255K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)

Press RETURN to get started!


*Mar 01, 05:22:49.2222:  %SYS-6-LOGGINGHOST_STARTSTOP: Logging to host 10.0.0.2 port 514 started - CLI
initiated
*Mar 01, 05:22:49.2222: %LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to
up
*Mar 01, 05:22:49.2222: %LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to
up

Router>enable
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface GigabitEthernet 0/0
Router(config-if)#ip address 192.168.1.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#interface GigabitEthernet 0/1
Router(config-if)#ip address 10.0.0.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#
```

```
Router(config)#access-list 101 deny tcp any any eq 23
Router(config)#access-list 101 deny tcp any any eq 21
Router(config)#access-list 101 permit ip any any
Router(config)#
```

Copy Paste

```
Router(config)#interface GigabitEthernet 0/1
Router(config-if)#ip access-group 101 in
Router(config-if)#exit
Router(config)#
```

Copy Paste

```
Router(config)#end
Router#
*Mar 01, 05:28:52.2828: SYS-5-CONFIG_I: Configured from console by console
Router#write memory
Building configuration...
[OK]
Router#
```

Command Prompt

```
Cisco Packet Tracer PC Command Line 1.0
C:\>telnet 192.168.1.2
Trying 192.168.1.2 ...
% Connection timed out; remote host not responding
C:\>
```

```
C:\>ping 192.168.1.2

Pinging 192.168.1.2 with 32 bytes of data:

Reply from 10.0.0.1: Destination host unreachable.
Reply from 10.0.0.1: Destination host unreachable.
Reply from 10.0.0.1: Destination host unreachable.
Reply from 10.0.0.1: Destination host unreachable.

Ping statistics for 192.168.1.2:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>
```

```
Router#show access-list
Extended IP access list 101
    10 deny tcp any any eq telnet (12 match(es))
    20 deny tcp any any eq ftp
    30 deny tcp any any eq www
    40 deny icmp any any (5 match(es))
    50 permit ip any any
```