










```
R1
R1#wri memory
Building configuration...
[OK]
R1#conf
R1#configure t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip dhcp pool HR
R1(dhcp-config)#network 50.0.1.128 255.255.255.192
R1(dhcp-config)#def
R1(dhcp-config)#default-router 50.0.1.129
R1(dhcp-config)#dns
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2 3
R1(dhcp-config)#exit
R1(config)# ip dhcp ex
R1(config)# ip dhcp excluded-address 50.0.0.129 50.0.1.139
R1(config)#exit
R1#wr
*Sep 10 12:59:10.806: %SYS-5-CONFIG_I: Configured from console by console
R1#wri me
R1#wri memory
Building configuration...
[OK]
R1#wri memory █
```

```
VPC-1

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.


VPCS is free software, distributed under the terms of the "BS
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.


Executing the startup file

VPC-1> ip dhcp
DDORA IP 50.0.1.140/26 GW 50.0.1.129

VPC-1> █
```



```
R1#
R1#conf
R1#configure t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#IP dhcp pool Sales
R1(dhcp-config)#network 50.0.0.0 255.255.255.0
R1(dhcp-config)#defa
R1(dhcp-config)#default-router 50.0.0.1
R1(dhcp-config)#dns
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2 3
R1(dhcp-config)#exit
R1(config)#ip dh
R1(config)#ip dhcp e
R1(config)#ip dhcp excluded-address 50.0.0.1 50.0.0.10
R1(config)#exit
R1#w
*Sep 10 13:40:28.631: %SYS-5-CONFIG_I: Configured from console by console
R1#wri me
R1#wri memory
Building configuration...
[OK]
R1#wri memory
```



 VPC-3

```
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.org)
All rights reserved.
```

```
VPCS is free software, distributed under the terms of the
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.
```

```
Press '?' to get help.
```

```
Executing the startup file
```

```
VPC-3> ip dhcp
DDORA IP 50.0.0.11/24 GW 50.0.0.1
```

```
VPC-3> █
```